

# **Awingu Admin Manual**

**Version 5.5**

1. Document Guidance	3
2. Portals	4
3. Installation	5
3.1 Connectivity Requirements	6
3.2 Sizing & Scaling Requirements	9
3.3 Deployment	13
3.3.1 Deployment on Microsoft Hyper-V	14
3.3.2 Deployment on VMware ESXi with vSphere Client on Windows	20
3.3.3 Deployment on VMware ESXi with vSphere Web Client	27
3.3.4 Deployment on Linux KVM	32
3.3.5 Deployment on Microsoft Azure	36
3.3.6 Deployment on Amazon EC2	37
3.3.7 Deployment on Google Compute	38
3.4 Awingu Installer	39
3.5 Azure Awingu All-In-One	45
4. System Settings	50
4.1 System Settings - Global	51
4.1.1 Connectivity Settings	52
4.1.2 General Information	56
4.1.3 Service Management Settings	58
4.1.4 Domain Settings	60
4.1.5 SSL Offloading Settings	64
4.1.6 Troubleshoot	68
4.2 System Settings - Configure	72
4.2.1 Branding Configuration	73
4.2.2 Feature Configuration	75
4.2.3 User Connector Configuration	78
4.3 System Settings - Manage	86
4.3.1 Application Management	87
4.3.2 Application Server Management	101
4.3.3 Category Management	105
4.3.4 Drive Management	106
4.3.5 File Type Management	108
4.3.6 Label Management	110
4.3.7 User Management	116
4.4 System Settings - Change Log	117
4.5 Service Provider Support in Awingu	119
5. Monitoring and Reporting	125
5.1 Status Overview of Services on All Servers	126
5.2 Monitoring Servers and Components	127
5.3 Awingu License Tracking	128
5.4 Live Monitoring of Users Activity	129
5.5 Monitoring the Application Connector	130
5.6 Insights Reporting	131
5.7 Audit Reporting	132
5.8 Anomaly Reporting	137
6. Integration	139
6.1 Integrating with existing Windows environment	140
6.2 Using Awingu on existing Citrix infrastructure	146
6.3 SSL offloader, reverse proxy or loadbalancer settings	152
6.4 Multi Factor Authentication	156
6.4.1 Using Awingu built-in OTP	157
6.4.2 Integrating Awingu with DUO	158
6.5 Awingu Single Sign On (SSO)	162
6.5.1 Enabling Pre-Authentication (PreAuth)	164
6.5.1.1 Setting up Azure AD as an external IDP for Awingu	170
6.5.1.2 Setting up Azure AD with OPSWAT as external IDPs for Awingu	171
6.5.1.3 Setting up ADFS as an external IDP for Awingu	172
6.5.1.4 Setting up ADFS with OPSWAT as external IDPs for Awingu	178
6.5.1.5 Setting up Google as an external IDP for Awingu	182
6.5.2 Enabling Single Sign-On (SSO)	184
6.6 Microsoft OneDrive for Business	191
6.7 Smart Card Redirection	193
6.8 Automate Awingu via the REST API	196
6.9 External Audit Logging	202
7. Backup and recovery of the Awingu Environment	208

## Document Guidance

<b>Introduction</b>	This document is an introduction to the Awingu Admin Guide which provides guidelines for integrators and customer system administrators for operating an Awingu environment.
<b>Related Documents</b>	<i>Awingu User Manual 5.5</i>
<b>Feedback</b>	We strive to continuously improve our products and to develop solutions that fit the needs of our customers. For questions or feedback on this document, please contact: <a href="mailto:feedback@awingu.com">feedback@awingu.com</a>
<b>Last Updated</b>	19/06/2023
<b>Contact Details</b>	<b>Awingu N.V.</b> Ottergemsesteenweg-Zuid 808, B44 9000 Gent Belgium Telephone: +32 (0) 9 296 40 11
<b>Intended Audience</b>	This guide is intended for Awingu integrators and system administrators.
<b>Confidentiality/Disclaimer</b>	All rights in and title to this document and all information contained and referenced within are owned by Awingu and its licensors unless expressly stipulated otherwise. This document is issued in confidence and must not be reproduced in whole or in part or given or communicated to any third party without the prior written consent of Awingu. It may not be used except for the restricted purpose for which it is made available to you. Awingu does not warrant that the information contained and referenced herein is accurate or complete, and nothing herein constitutes investment, tax, legal or other advice, nor should it be relied on in making an investment or other decision. Awingu shall not be liable for any loss, expense, damage or claim arising from the statements made or omitted to be made, or advice given or omitted to be given in this document.

# Portals

## Parallels My Account

Navigate to [my.parallels.com](https://my.parallels.com) to access Parallels My Account. Signing in is required to be able to manage the **licenses** of an organization, as well as create **support requests** which will be handled by our support team.

## Knowledge base

There is a publicly available **knowledge base** that can be found at [kb.parallels.com](https://kb.parallels.com) . It contains articles on very specific issues or procedures, frequently asked questions, and step-by-step tutorials on how to accomplish certain configurations, ...



# Installation

## Introduction

This guide describes how you can install and deploy the Awingu virtual machine.

- [Connectivity Requirements](#)
- [Sizing & Scaling Requirements](#)
- [Deployment](#)
- [Awingu Installer](#)
- [Azure Awingu All-In-One](#)

## Connectivity Requirements

### Introduction

Before starting a deployment of the Awingu platform, a few connectivity requirements need to be checked and/or enabled. Please review this section to ensure proper installation and operation.

### Connectivity Requirements during Installation:

During installation of the Awingu appliance as virtual machine (VM), we need to be able to have a connection to Awingu's repository servers and sync to the right time-zone.

Connection	From	To
NTP: UDP port 123	The Awingu VM	On- or off-site NTP service. A common use case is to use the NTP service of the AD servers. The NTP service should use the same time zone as the hypervisor (UTC is recommended).
DNS: UDP port 53	The Awingu VM	DNS server which resolves the NTP (when provided via FQDN*) and Awingu's repository servers (repo-pub.awingu.com). A common use case is to use the DNS service of the AD service.
HTTP : TCP port 8080	The browser of the admin	The Awingu VM
HTTP : TCP port 80	The browser of the admin	The Awingu VM

\* FQDN = Fully Qualified Domain Name, e.g. [ntp.mycompany.com](http://ntp.mycompany.com)

### Connectivity Requirements during Operation and Configuration:

The Awingu appliance has a few requirements for correct operation. Before deployment, check whether the following ports can be opened.



**Best practice:** configure your firewall rules to only allow traffic from/to the ports which are needed for operation.

Connection	From	To
LDAP(S): TCP port 389 (or TCP port 636 for SSL encryption)	The Awingu VM	LDAP or Active Directory server(s) back-end
Kerberos: UDP/TCP port 88 and TCP port 464	The Awingu VM	Kerberos server (Only required when users need to be able to change password at next logon) <b>Important:</b> The Kerberos server should also have PTR (reverse DNS) and SRV records in place to locate the KDC server and define the protocol to use**
RADIUS (if used): UDP port 1812	The Awingu VM	RADIUS service for second factor authentication
CIFS (if used): UDP port 137, TCP port 445	The Awingu VM	CIFS/SMB file server(s) back-end
WebDAV (if used): TCP port 80 or 443 (or different depending on WebDAV config)	The Awingu VM	WebDAV file server(s) back-end
RDP: TCP port 3389 (RDP /RemoteApp)	The Awingu VM	To application server(s) back-end
NTP: UDP port 123	The Awingu VM	On- or off-site NTP service. A common use case is to use the NTP service of the AD server.

HTTPS: TCP port 443	The Awingu VM	<ul style="list-style-type: none"> <li>Awingu's repository servers: <a href="https://repo-pub.awingu.com">https://repo-pub.awingu.com</a> (directly or via the configured HTTP proxy - see <a href="#">Connectivity Settings</a>).</li> <li>Only mandatory during upgrades, but required for Anonymous Usage Reporting.</li> <li>When using SaaS services, those services need to be reachable by Awingu or via the configured HTTP proxy (see <a href="#">Connectivity Settings</a>): <ul style="list-style-type: none"> <li><b>Microsoft OneDrive for Business:</b> <ul style="list-style-type: none"> <li>&lt;mydomain&gt;-my.sharepoint.com</li> <li>login.microsoftonline.com</li> <li>graph.microsoft.com</li> </ul> </li> <li><b>DUO Multi-Factor Authentication:</b> <ul style="list-style-type: none"> <li>&lt;your_api&gt;.duosecurity.com</li> </ul> </li> <li>Automatic certificates through Let's Encrypt (see <a href="#">Certificate Settings</a>): <ul style="list-style-type: none"> <li>*.api.letsencrypt.org (⚠ only directly, not through HTTP proxy)</li> </ul> </li> </ul> </li> </ul>
HTTP(S): TCP port 80/443	The Awingu VM	Web applications reversed proxied by Awingu
DNS: UDP port 53	The Awingu VM	DNS server which resolves all connections mentioned above (when provided as FQDN*)
HTTP: TCP port 80 (long living WebSocket)	The (end user browser) client***	<ul style="list-style-type: none"> <li>The Awingu VM</li> <li>When using automatic certificates (see <a href="#">Certificate Settings</a>): the servers of Let's Encrypt</li> </ul>
HTTPS: TCP port 443 (long living WebSocket)	The (end user browser) client***	<ul style="list-style-type: none"> <li>The Awingu VM (Only when SSL Offloader enabled in <a href="#">Connectivity</a> section)</li> <li>When using automatic certificates (see <a href="#">Certificate Settings</a>): the servers of Let's Encrypt</li> </ul>
SNMP (if used): UDP port 161	Monitoring System	The Awingu VM (Only if SNMP enabled in <a href="#">Connectivity</a> section)
HTTP(s) : TCP port 80/443	All servers involved in Kerberos Authentication (AD and Application Servers)	The Awingu VM ( http(s)://<AWINGU_URL>/crl/<AWINGU_DOMAIN_NAME>.crl )
SSH: TCP port 22	The client	The Awingu VM (Only necessary to access Awingu using SFTP to obtain the backup of the Awingu database)

\* FQDN = Fully Qualified Domain Name, e.g. [ntp.mycompany.com](http://ntp.mycompany.com)

\*\* e.g. [kerberos-master.\(tcp|udp\).staging.awingu.com](https://kerberos-master.(tcp|udp).staging.awingu.com) - For more information: <https://technet.microsoft.com/en-us/library/cc961719.aspx>

\*\*\* When this connection goes via an SSL-offloader, reverse proxy, firewalls, etc., please make sure that WebSockets are supported and that open WebSocket connections are not killed after a while. See [SSL offloader](#), [reverse proxy](#) or [loadbalancer settings](#) for other important settings.



For **multi node** deployment, all TCP, UDP and ICMP traffic should be allowed between the nodes. This traffic is not encrypted. Each node has an internal firewall only allowing traffic from other nodes (based on the IP address).



While the Awingu appliance always listens for incoming requests on ports 80 (HTTP) or 443 (HTTPS), port forwarding originating from a different port is supported, e.g. <https://awingu.company.com:8443>.

Note: Using Awingu as an IdP in combination with accessing Awingu on an different port than 80 or 443 is not tested.

#### Connectivity Requirements only during Remote Intervention:

In some cases, the Awingu support team will request direct SSH access to the Awingu appliance. For security, the appliance only allows access using public key authentication (with an optional [intervention password](#) on top of the public key authentication).

Connection	From	To
------------	------	----

SSH: TCP port 22	Awingu headquarters ( IP address will be provided by support )	The Awingu VM
------------------	--	---------------

## Sizing & Scaling Requirements

### Standard (minimum) setup

For a standard single node setup, the minimum sizing requirements are:

- 2 vCPUs
- 4 GB of memory
- 80 GB of disk space

### Scaling

An Awingu setup can scale on 3 levels:

#### 1) In the appliance

By adding more memory / CPU to a virtual appliance



When adding extra resources like CPU and memory to an appliance, Awingu will be able to handle more RDP streams and file operations.

The 8 CPU / 8 GB is not a hard limit, but in general for environments with more than 500 concurrent RDP streams we recommend to go to 3 medium servers rather than to grow the single node.


#### 2) In the cluster

Awingu can be configured in multi node setup. See [Service Management Settings](#) for instructions how to do this. In such a setup, multiple Awingu nodes form a cluster. By adding more nodes to the cluster you can scale out your Awingu setup. Adding extra nodes can be done at any time without service impact if the nodes are front-end only nodes.

For this scenario Awingu assumes that:


- all data is stored in an external database
- there is a load balancer in front of Awingu to load the incoming requests over the different Awingu virtual appliances

For a cluster setup there is only 1 system settings and 1 dashboard, so all changes are applied automatically to all nodes of the cluster. When upgrading to a new version, the full cluster will be upgraded at the same time.



### 3) Making multiple clusters pointing to the (same) Windows backend

Multiple, independent clusters can point to the same Windows backend since there is no Awingu software required on those back-end servers.



When going to multiple clusters, the configuration of each cluster needs to be maintained separately. If needed this can be (partially) automated via the Awingu API. (See [Automate Awingu via the REST API](#))

#### Sizing Parameters

**The sizing of an Awingu environment is mainly determined by:**

- The amount of concurrent RDP streams (number of RDP sessions going from the Awingu appliance to the Windows back end(s))

- Type of RDP / Remote apps published behind Awingu (apps with lots of screen updates will require more resources than traditional business apps)
- The amount of concurrent file operations (generating previews and file shares)
- Size of the file operations (small files will require less resources than large files)

Next to this other factors may influence the Awingu sizing:

- CPU speed / Type
- Overall performance of the underlying storage system
- Overall load on the hypervisor
- High Availability (HA) requirements

For simplicity reasons we have mapped these parameters to 2 user profiles:

- **Light Concurrent User:** User who has 1 RDP stream open and does not use the file operations heavily. This is typically the case when publishing VDIs or when all remote apps in a collection are [merged into a single RDP stream](#).
- **Heavy Concurrent User:** User who has 3 RDP streams open, 10 accesses to reverse proxied web applications and does a number of file operations per hour per user.

Also note that all recommendations are based on concurrent users. A concurrent user is a user that is logged in to the Awingu appliance and that has at least 1 application running.

Next to this we highly recommend to measure the overall Awingu appliance resource consumption from time to time and to add extra resources when needed.

### Single node Awingu

In a single node set-up, all processes are running on a single VM (frontend role, backend role and database role). This architecture can support only a limited number of the concurrent users. This has resulted in the following deployment recommendations:

	Concurrent Light Users	Concurrent Heavy Users
2 vCPU + 4 GB memory	100	50
8 vCPU + 8 GB memory	500	100

**Note that 4 GB of RAM is a hard minimum!**

### Multi node Awingu

Once one Awingu appliance has been installed, you can add other appliances to it to have a multi node Awingu environment (see [Service Management Settings](#)). Note that you need a load balancer to balance over the nodes with Frontend roles (see [SSL offloader, reverse proxy or loadbalancer settings](#)).

Each appliance can have either just a frontend role; or both a frontend and a backend role:

- The **frontend role** takes care of all RDP and file activity. You need at least 1 of these roles and the more concurrent users you have, the more appliances with these roles you need to deploy
- The **backend role** takes care of the auditing. In a multi node deployment there can only be 1 or 3 back-end nodes. No other combinations are allowed.

Next to the Frontend & Backend role there is also a **database role**: when deploying your first Awingu node there is the option to use the built-in database or go for an [external database](#). This database contains the Awingu configuration and not the audit logs as these are stored in the backend roles. Note it is not possible to change from an internal database to an external database once installation has finished.

If High Availability (HA) is required, i.e. service interruption is not allowed (except during upgrades), you need at least 3 nodes and an external database (cf. [Installation](#)). Note that if an appliance goes down and the [Application Sessions Failover](#) feature is enabled, users on that node will be disconnected for a few seconds and then be reconnected to an other node. When the feature is not enabled, user sessions on the failing node will be lost and users will have to login in again and restart their apps.

We assume in a multi node environment all nodes are 8 vCPU and 8 GB Memory. The sizing below is for normal operations. In case a node goes down, the capacity will be reduced to the capacity of the cluster with 1 node less.

	Roles Configuration	Concurrent Light Users	Concurrent Heavy Users
2 nodes (*)	node 1: Front + Back node 2: Front	1.000	200
3 nodes	node 1,2 & 3 : Front + Back	1.500	300
4 nodes	node 1,2 & 3 : Front + Back node 4: Front	2.000	400
5 nodes	node 1,2 & 3 : Front + Back node 4,5 : Front	2.500	500
...		+ 500	+ 100
10 nodes	node 1,2 & 3 : Front + Back node 4-10: Front	5.000	1.000

(\*) A 2-node Awingu cluster has no HA. If the first node goes down, there will also be impact on the second node as there are no back-end roles available anymore at this time.

Although 10 nodes is not a hard limit we recommend not to go above 10 nodes in a single Awingu cluster. If more users are needed we recommend to setup a second cluster and connect it to the same Windows back end.

It is recommended to distribute the back-end roles over three differently powered racks to avoid split brain scenarios.

## Backup strategy for multi nodes

It is always a good practice to regularly back up your Awingu environment, especially before upgrades. If your hypervisor allows **consistent** live snapshots, you can use that feature. If consistency is not guaranteed, then you need to snapshot/back up as follows:

- For back-end nodes: please **sequentially** do following actions for each node
  1. Shutdown **one** node
  2. Snapshot/back up the node
  3. Start the node
  4. Wait until all services in the Dashboard are green.
- For front-end nodes: you can shutdown and start them up all at once.
- If you have an external database, please use the snapshot feature of the database to create a consistent snapshot.



## Deployment

Awingu provides virtual appliances that are custom-built to run on four commonly used hypervisors and on three major cloud platforms.

To begin installing the Awingu platform, download the virtual appliance for your hypervisor. Import and start the appliance and open your browser to proceed with your installation through the System Settings.



### Supported hypervisors

Microsoft Hyper-V Server: 2016 and 2019  
VMware ESXi: 7.0 - 8.0  
KVM  
Citrix Hypervisor: 8.2 (deprecated)

Images of the Awingu appliances can be found at <https://repo-pub.awingu.com/appliances/>

### Supported cloud platforms

Microsoft Azure  
Amazon EC2  
Google Compute Engine

- [Deployment on Microsoft Hyper-V](#)
- [Deployment on VMware ESXi with vSphere Client on Windows](#)
- [Deployment on VMware ESXi with vSphere Web Client](#)
- [Deployment on Linux KVM](#)
- [Deployment on Microsoft Azure](#)
- [Deployment on Amazon EC2](#)
- [Deployment on Google Compute](#)

## Deployment on Microsoft Hyper-V

In this guide we will show you how to deploy the Awingu appliance on Microsoft Hyper-V hypervisor using Microsoft Hyper-V manager.


- [Step 1 - Download and extract the Awingu appliance](#)
- [Step 2 - Create a VM with the VHD image in Hyper-V manager](#)
- [Step 3 - Boot the Awingu virtual machine](#)

### Step 1 - Download and extract the Awingu appliance


Download the Awingu appliance from the Awingu repository server at <https://repo-pub.awingu.com/appliances/latest/hyperv/> and extract the ZIP file to obtain the VHD.

### Step 2 - Create a VM with the VHD image in Hyper-V manager


1. Import the VHD image in Hyper-V manager by navigating to **New > Virtual Machine ...**




2. Specify a name for the Awingu virtual machine.



3. Assign memory to the Awingu virtual machine. Specify RAM and CPU settings for your VM. See [Sizing & Scaling Requirements](#) to determine the hardware requirements.



4. Configure networking for your Awingu virtual machine



5. Connect to a virtual hard disk by selecting the option Use an existing virtual hard disk. Select the unzipped VHD file.

**New Virtual Machine Wizard**

### Connect Virtual Hard Disk

Before You Begin  
Specify Name and Location  
Assign Memory  
Configure Networking  
**Connect Virtual Hard Disk**  
Summary

A virtual machine requires storage so that you can install an operating system. You can specify the storage now or configure it later by modifying the virtual machine's properties.

☐ Create a virtual hard disk

Name:

Location:

Size:  GB (Maximum: 2040 GB)

☒ Use an existing virtual hard disk

Location:

☐ Attach a virtual hard disk later

< Previous   Next >   Finish   Cancel

6. Review your virtual machine settings.

**New Virtual Machine Wizard**

### Completing the New Virtual Machine Wizard

Before You Begin  
Specify Name and Location  
Assign Memory  
Configure Networking  
Connect Virtual Hard Disk  
**Summary**

You have successfully completed the New Virtual Machine Wizard. You are about to create the following virtual machine.


Description:

Name: awingu22-VM  
Memory: 2048 MB  
Network: External Network 2  
Hard Disk: \\hyper-v-node\C\$\images\test\awingu\_hyperv\awingu\_hyperv\Virtual H

To create the virtual machine and close the wizard, click Finish.

< Previous   Next >   **Finish**   Cancel


7. Right click on the Awingu Virtual machine and click **Settings...**




8. Please edit the settings of the Awingu VM to specify the memory and CPU settings.

**IMPORTANT** In memory management, make sure you select `Static`. Dynamic memory allocation is not supported in Hyper-V Manager for Debian-based Linux systems, so selecting `Dynamic` will result in errors on your VM.

10.




11. Disable Secure boot in the Security section of the settings when using Generation 2 VMs



### Step 3 - Boot the Awingu virtual machine

1. Open a console to connect to the virtual machine.
2. Configure the virtual machine network settings. You can choose to use either a static IP or a dynamic IP assigned by DHCP.



3. After you have configured your network settings, you are now ready to proceed with the installation through a graphical installer interface. If you need to change your network settings in the future, you can update these here again (not supported for multi node configuration). In order to connect to the graphical installer interface, open a web browser and browse to the IP of the Awingu virtual machine on port 8080. More information about how to proceed with the install can be found [here](#).


## Deployment on VMware ESXi with vSphere Client on Windows

In this guide we will show you how to install and deploy the Awingu appliance on VMware ESXi hypervisor.

- [Step 1 - Import the appliance in VMware vSphere Client](#)
- [Step 2 - Configure your Awingu virtual machine settings](#)
- [Step 3 - Start up your Awingu virtual machine](#)

### Step 1 - Import the appliance in VMware vSphere Client


1. Connect to your vSphere ESXi hypervisor using vSphere Client
2. Open the OVF deployment menu



3. Import the Awingu OVF template from the Awingu repo server
  - a. Go to <https://repo-pub.awingu.com/appliances/latest/> and browse to the ESX directory.




- b. Select the OVA file you want to download and copy-paste this URL in your VMware client import menu:



- c. Alternatively, you can download the OVA file and use it via the Browse... button.

4. Verify the template details



5. Enter the name for your Awingu virtual machine

The screenshot shows the 'Deploy OVF Template' wizard at the 'Name and Location' step. The left sidebar contains links for 'Source', 'OVF Template Details', 'Name and Location' (selected), 'Storage', 'Disk Format', 'Network Mapping', and 'Ready to Complete'. The main area has a 'Name:' text box with 'awingu-vm' entered. Below it, a note states: 'The name can contain up to 80 characters and it must be unique within the inventory folder.' At the bottom are 'Help', '< Back', 'Next >', and 'Cancel' buttons.

**Deploy OVF Template**

**Name and Location**  
Specify a name and location for the deployed template

Source  
OVF Template Details  
**Name and Location**  
Storage  
Disk Format  
Network Mapping  
Ready to Complete

Name:  
awingu-vm  
The name can contain up to 80 characters and it must be unique within the inventory folder.

Help < Back Next > Cancel

6. Select the data storage where you want to store your virtual machine

The screenshot shows the 'Deploy OVF Template' wizard at the 'Storage' step. The left sidebar is the same as the previous step, with 'Storage' now selected. The main area asks 'Where do you want to store the virtual machine files?'. It features a table titled 'Select a destination storage for the virtual machine files:' with columns: Name, Drive Type, Capacity, Provisioned, Free, Type, Thin Provisioning, and Access. Two rows are listed: 'datastore1' and 'datastore2'. Below the table is a checkbox 'Disable Storage DRS for this virtual machine' and another table titled 'Select a datastore:' with the same column headers but no data rows. At the bottom are 'Help', '< Back', 'Next >', and 'Cancel' buttons.

**Deploy OVF Template**

**Storage**  
Where do you want to store the virtual machine files?

Source  
OVF Template Details  
Name and Location  
**Storage**  
Disk Format  
Network Mapping  
Ready to Complete

Select a destination storage for the virtual machine files:

Name	Drive Type	Capacity	Provisioned	Free	Type	Thin Provisioning	Access
datastore1	SSD	216.00 GB	127.64 GB	92.68 GB	VMFS5	Supported	Single host
datastore2	SSD	111.75 GB	972.00 MB	110.80 GB	VMFS5	Supported	Single host

☐ Disable Storage DRS for this virtual machine

Select a datastore:

Name	Drive Type	Capacity	Provisioned	Free	Type	Thin Provisioning	Access
------	------------	----------	-------------	------	------	-------------------	--------

Help < Back Next > Cancel

7. Select "Thin provision"


The screenshot shows the 'Deploy OVF Template' window with the 'Disk Format' tab selected. The window title is 'Deploy OVF Template'. The sub-header is 'Disk Format' with the question 'In which format do you want to store the virtual disks?'. On the left, a sidebar lists steps: 'Source', 'OVF Template Details', 'Name and Location', 'Storage', 'Disk Format' (highlighted), 'Network Mapping', and 'Ready to Complete'. The main area shows 'Datastore:' as 'datastore1' and 'Available space (GB):' as '92.7'. Three radio buttons are present: 'Thick Provision Lazy Zeroed', 'Thick Provision Eager Zeroed', and 'Thin Provision' (which is selected). At the bottom, there are 'Help', '< Back', 'Next >', and 'Cancel' buttons.

8. Set network mode for your virtual machine to "bridged"


The screenshot shows the 'Deploy OVF Template' window with the 'Network Mapping' tab selected. The window title is 'Deploy OVF Template'. The sub-header is 'Network Mapping' with the question 'What networks should the deployed template use?'. On the left, a sidebar lists steps: 'Source', 'OVF Template Details', 'Name and Location', 'Storage', 'Disk Format', 'Network Mapping' (highlighted), and 'Ready to Complete'. The main area has the instruction 'Map the networks used in this OVF template to networks in your inventory'. It contains a table with two columns: 'Source Networks' and 'Destination Networks'. The first row shows 'bridged' under 'Source Networks' and 'VM Network' under 'Destination Networks'. Below the table is a 'Description:' label and a text area containing 'The bridged network'. At the bottom, there are 'Help', '< Back', 'Next >', and 'Cancel' buttons.

Source Networks	Destination Networks
bridged	VM Network

9. Review your configuration and go back to change details if needed




10. Click finish to start download and deploy the Awingu appliance. This step may take several minutes. Do **not start** the machine automatically after deployment.




## Step 2 - Configure your Awingu virtual machine settings

1. Right-click on the Awingu-VM to change the settings for RAM and CPUs:




2. You can now allocate memory and CPU sources to the Awingu Virtual Machine



See [Sizing & Scaling Requirements](#) to determine the hardware requirements.


3. When the host's memory is almost full, ESXi will start doing memory ballooning on the Virtual Machines. Ballooning is not recommended for the Awingu. To avoid this, you can reserve all memory:




It is recommended to set the storage controller type to VMWare Paravirtual if this is not the case yet. Awingu 5.3 appliances will use the recommended storage controller type by default.

### Step 3 - Start up your Awingu virtual machine

1. Start up the virtual machine in your VMware inventory view and open the console of the Awingu virtual machine



2. After booting the machine you should be presented a network configuration menu where you can choose to use a static IP address or to use a dynamic IP address assigned through DHCP:



3. After you have configured your network settings you can now go to the graphical installation interface. If you need to change your network settings in the future, you can update these here again (not supported for multi node configuration). More detailed instructions how to proceed with the graphical installer interface can be found in the [next section](#).


## Deployment on VMware ESXi with vSphere Web Client

In this guide we will show you how to install and deploy the Awingu appliance on VMware vCenter.

- [Step 1 - Import the appliance in VMware vSphere Client](#)
- [Step 2 - Configure your Awingu virtual machine settings](#)
- [Step 3 - Start up your Awingu virtual machine](#)

### Step 1 - Import the appliance in VMware vSphere Client

1. Connect to vCenter using vSphere Client (HTML5 or Flash)
2. In the left column, navigate to your hypervisor, right-click and select *Deploy OVF Template...*



3. Import the Awingu OVF template from the Awingu repo server
  - a. Go to <https://repo-pub.awingu.com/appliances/latest/> and browse to the ESX directory.
  - b. Select the OVA file and copy-paste this URL the *Deploy OVF Template* wizard:  
E.g.: <https://repo-pub.awingu.com/appliances/latest/esx/awingu-4-0-1.ova>

### Deploy OVF Template

1 Select an OVF template

2 Select a name and folder

3 Select a compute resource

4 Review details

5 Select storage

6 Select networks

7 Ready to complete

Select an OVF template

Select an OVF template from remote URL or local file system

Enter a URL to download and install the OVF package from the Internet, or browse to a location accessible from your computer, such as a local hard drive, a network share, or a CD/DVD drive.

☒ URL

☐ Local file

https://repo-pub.awingu.com/appliances/latest/esx/awingu\_vmx11.ova

Choose Files No file chosen

CANCEL

BACK

NEXT

- c. Alternatively, you can download the OVA file upload it via the *Local file* option.

4. Enter the name for your Awingu virtual machine and select the location.

### Deploy OVF Template

✓ 1 Select an OVF template

**2 Select a name and folder**

3 Select a compute resource

4 Review details

5 Select storage

6 Select networks

7 Ready to complete

Select a name and folder

Specify a unique name and target location

Virtual machine name:

Select a location for the virtual machine.

172.18.0.30

Awingu-DC

CANCEL

BACK

NEXT

5. Select the hypervisor to deploy on.

### Deploy OVF Template

✓ 1 Select an OVF template

✓ 2 Select a name and folder

**3 Select a compute resource**

4 Review details

5 Select storage

6 Select networks

7 Ready to complete

Select a compute resource

Select the destination compute resource for this operation

Awingu-DC

Awingu-EU01

172.18.0.10

172.18.0.11

172.18.0.12

Compatibility

✓ Compatibility checks succeeded.

CANCEL

BACK

NEXT

6. Review the details.

### Deploy OVF Template

✓ 1 Select an OVF template

✓ 2 Select a name and folder

✓ 3 Select a compute resource

**4 Review details**

5 Select storage

6 Select networks

7 Ready to complete

Review details

Verify the template details.

Publisher	No certificate present
Download size	1.8 GB
Size on disk	4.0 GB (thin provisioned) 73.2 GB (thick provisioned)

CANCEL

BACK

NEXT



7. Select the storage options and location. Note that Thin Provisioning works fine.

### Deploy OVF Template

- ✓ 1 Select an OVF template
- ✓ 2 Select a name and folder
- ✓ 3 Select a compute resource
- ✓ 4 Review details
- 5 Select storage**
- 6 Select networks
- 7 Ready to complete

**Select storage**  
Select the datastore in which to store the configuration and disk files

Select virtual disk format:

VM Storage Policy:

Name	Capacity	Provisioned	Free
ESX1-Root	22.25 GB	932 MB	21.3
ESX1-Storage	894 GB	1.29 TB	156

Compatibility

✓ Compatibility checks succeeded.

[CANCEL](#) [BACK](#) [NEXT](#)

8. Set network mode for your virtual machine to "bridged". You don't need to provide an IP address.

### Deploy OVF Template

- ✓ 1 Select an OVF template
- ✓ 2 Select a name and folder
- ✓ 3 Select a compute resource
- ✓ 4 Review details
- ✓ 5 Select storage
- 6 Select networks**
- 7 Ready to complete

**Select networks**  
Select a destination network for each source network.

Source Network	Destination Network
bridged	VM Network

1 items

**IP Allocation Settings**

IP allocation:  IP address:

IP protocol:

[CANCEL](#) [BACK](#) [NEXT](#)

9. Review your configuration and go back to change details if needed.

### Deploy OVF Template

- ✓ 1 Select an OVF template
- ✓ 2 Select a name and folder
- ✓ 3 Select a compute resource
- ✓ 4 Review details
- ✓ 5 Select storage
- ✓ 6 Select networks
- 7 Ready to complete**

**Ready to complete**  
Click Finish to start creation.


Provisioning type	Deploy OVF From Remote URL
Name	awingu-VM
Template name	awingu_vmx8
Folder	Awingu-DC
Resource	172.18.0.10
Location	ESX1-Storage

[CANCEL](#) [BACK](#) [FINISH](#)

10. Click finish to start download and deploy the Awingu appliance. This step may take several minutes. Do **not start** the machine yet.

## Step 2 - Configure your Awingu virtual machine settings


1. Right-click on the Awingu-VM to change the settings for RAM and CPUs:



2. You can now allocate memory and CPU sources to the Awingu Virtual Machine

See [Sizing & Scaling Requirements](#) to determine the hardware requirements.


When the host's memory is almost full, ESXi will start doing memory ballooning on the Virtual Machines. Ballooning is not recommended for the Awingu. To avoid this, you can reserve all memory.




It is recommended to set the storage controller type to VMWare Paravirtual if this is not the case yet. Awingu 5.3 appliances will use the recommended storage controller type by default.

### Step 3 - Start up your Awingu virtual machine

1. Power On your Awingu VM
2. Open the console by clicking on the thumbnail on the right pane.



3. After booting the machine you should be presented a network configuration menu where you can choose to use a static IP address or to use a dynamic IP address assigned through DHCP.



4. After you have configured your network settings you can now go to the graphical installation interface. If you need to change your network settings in the future, you can update these here again (not supported for multi node configuration). More detailed instructions how to proceed with the graphical installer interface can be found in the [next section](#).

## Deployment on Linux KVM

By far the easiest way to deploy the Awingu appliance on a Linux KVM hypervisor is by using virt-manager to import and deploy the Awingu appliance. In this guide we will show you which steps you need to perform.


- [Step 1 - Install KVM on your linux system.](#)
- [Step 2 - Download the Awingu appliance](#)
- [Step 3 - Install and configure virt-manager](#)

### Step 1 - Install KVM on your linux system.


Make sure you have KVM installed on your Linux system. In case you haven't installed KVM, you can install KVM as follows:

```
# on debian-based systems
sudo apt-get install qemu-kvm
```

```
# on Red Hat-based systems
sudo yum install qemu-kvm
```

 Before you install KVM, make sure your virtualization host supports hardware-assisted virtual virtualization. If you find "svm" or "vmx" in the file /proc/cpuinfo, then your host supports hardware-assisted virtualization. You can check whether one of these flags is present by executing the following command:

```
grep "svm\|vmx" /proc/cpuinfo
```


 It is not recommended to do memory ballooning on the Awingu appliances.

### Step 2 - Download the Awingu appliance

Check <https://repo-pub.awingu.com/appliances/latest/kvm/> to see the latest version available and copy-paste the URL to the qcow2 file.

```
wget https://repo-pub.awingu.com/appliances/latest/kvm/awingu-5-2-4.qcow2
mv awingu-5-2-4.qcow2 /var/lib/libvirt/images
```

### Step 3 - Install and configure virt-manager

 Virt-manager is a graphical front-end to libvirt, which interacts with the KVM hypervisor. You can use virt-manager to manage all your virtual machines running on KVM.

1. To install virt-manager run the following commands:


```
# on debian-based systems
sudo apt-get install virt-manager

# on Red Hat-based systems
sudo yum install virt-manager
```


2. After the installation, you need to make sure you start up virt-manager as root

```
sudo virt-manager
```


3. Connect to your KVM hypervisor (either on local machine or remote host)
4. Click the icon in the upper left corner to create a new virtual machine.




5. Browse to the location containing the Awingu QCOW image and specify the following configuration:
  - a. OS type: Linux
  - b. Version: Ubuntu 18.04
6. See [Sizing & Scaling Requirements](#) to determine the hardware requirements.




7. Review your virtual machine settings. You don't need to change the advanced options.



8. After you have finished you have reviewed your virtual machine configuration, press the finish button, The Awingu Appliance will get imported and start to boot. This may take several minutes.




9. When the machine has booted up, you will see a network configuration menu where you can choose to use either a static IP or a dynamic IP assigned by DHCP.



10. After you have configured the network settings for your virtual machine, you can now proceed with the installation through a graphical installer interface. If you need to change your network settings in the future, you can update these here again (not supported for multi node configuration).

To access the graphical installer interface you need to open a web browser and go to the IP of your virtual machine on port 8080. More detailed instructions how to proceed with the graphical installer interface can be found in the [next section](#).

## Deployment on Microsoft Azure

 You need to use premium storage to use Awingu.

### Deploying using the Azure Resource Manager (ARM)

The Awingu appliance is available via the Azure Marketplace

We have an Azure Marketplace Solution **Awingu all-in-one**, ideal to kick-start using Awingu:

- Deploys and configures a Windows environment:
  - Windows Active Directory server with file server
  - Windows Application Server
- Deploys and configures an Awingu environment



## Deployment on Amazon EC2

Links to the correct Amazon images can be found directly on: <https://repo-pub.awingu.com/appliances/latest/ec2>



### **Amazon CloudWatch**

The Amazon Cloudwatch Agent has been installed on the Amazon image by default. This allows you to monitor the disk and memory usage.

## Deploying using the Google Compute VM Instances Interface

Navigate to <https://repo-pub.awingu.com/appliances/latest/gce/> in your web browser and download the most recent .tar.gz file.

You can import this image file into your Google Compute environment by following Google's official instructions. <https://cloud.google.com/compute/docs/import/import-existing-image>

After importing the image, create a new VM instance using this image, you will then be able to connect to the appliance's IP address (followed by port 8080) in your browser to configure the Awingu appliance.

# Awingu Installer

- Accessing the installer
- Step 1 - End User License Agreement
- Step 2 - Restore Backup (optional)
- Step 3 - Setup Management User
- Step 4 - Server Configuration
- Step 5 - Database Configuration
- Step 6 - Summary
- Installation Progress
- Install complete

## Accessing the installer

After [deploying an Awingu appliance](#) you can access the web-based installer by navigating to the appliance on port 8080 using one of the supported laptop browsers. It is important to note that, although the Awingu interface will work on any device or browser, the install wizard is not meant to be used on mobile or tablet devices.

- Open your browser
- Enter `http://<appliance ip or dns>:8080/` in the address bar

You will be presented with the first step of the installation wizard.

All information entered in the wizard is required to bootstrap your Awingu platform. After the installation, you can review and modify all information in the [System Settings](#).

## Step 1 - End User License Agreement

End User License Agreement

AWINGU

END USER LICENSE AGREEMENT (V5.0.0)

This End User License Agreement ("EULA") is a legal agreement between:

- you (both the individual installing the Software and any other person or entity on behalf of which such individual is acting) ("you" or "End User"); and
- Awingu NV, a limited liability company incorporated under the laws of Belgium, with registered seat at Ottergemsesteenweg-Zuid 808 bus 44, B-9000 Gent, Belgium and registered with the Crossroad Bank for Enterprises under company number VAT BE 0832 589 222 (Register of Legal Persons (RPR) Oost-Vlaanderen, Gent) ("Awingu").

governing your acquisition and use of Awingu's proprietary Software (as defined hereinafter), either directly from Awingu or indirectly through a Reseller.

**1. DEFINITIONS**

1.1 "Concurrent User" means any individual user of the Software who is authorized by an End User to access or use the Software, it being understood that each simultaneous login to the Software (through active browser sessions) shall be deemed to constitute one Concurrent User. Hence, when one user is simultaneously logged in to the Software from two different devices, this constitutes two Concurrent User sessions;

1.2 "Confidential Information" means the Software, its source code, the content of the Documentation, any financial, statistical, business, technical, copyright, and confidential or proprietary information relating to the Software or to Awingu's business, software, products and/or services, which is disclosed by Reseller, Awingu or its affiliates to End User, or which is deduced from the Software or Awingu's business, software, products and/or services by End User;

1.3 "Delivery Date" means the date on which the relevant License keys are being activated by or in the name and on behalf of the End User;

1.4 "Documentation" means all of Awingu's user manuals, operating instructions and other documents relating to the Software, as generally made available from time to time to End Users;

1.5 "End User" means the final purchaser or licensee acquiring a License either (1) for a certain number of its own internal Concurrent Users or Named Users; or (2) for certain third-party Concurrent Users or Named Users acquiring remote access to the Software as part of End User's hosting deployment;

1.6 "Fees" means the Subscription License Fees, Perpetual License Fees, Maintenance and Support Fees or Other Fees as defined in this EULA;

1.7 "Initial License Term" means, with respect to a Subscription License, the initial minimum fixed license term as set out in the Order Form during which the Software is licensed to End User, as further described in Section 12.1;

1.8 "Initial Maintenance Period" means, with respect to a Perpetual License, the mandatory Maintenance Period of one year or three years, as further defined in the Order Form, beginning on the Delivery Date;

1.9 "License" means either the Perpetual or the Subscription License granted by Awingu to End User in view of using and accessing the Software and the Documentation, as further described in Section 3;

1.10 "License Fees" means the fees due by End User for the License, which are payable to the Reseller (or, when purchased directly from Awingu, to Awingu);

1.11 "License Term" means, (i) in respect of a Subscription License, the Initial License Term and the Subsequent License Term(s) (if any); and (ii) in respect of a Perpetual License, the indefinite term commencing on the Delivery Date;

1.12 "Maintenance Period" means (i) in respect of a Subscription License, the term corresponding to the License Term; and (ii) in respect of a Perpetual License, the Initial Maintenance Period and the Subsequent Maintenance Period(s) (if any), within which First

☐ Yes, I have read and hereby accept the above license terms and conditions.

Previous

Next

Finish

Before starting the actual setup of the appliance, you have to accept the *End User License Agreement*.

The EULA can also be found on the [Awingu website](#).

If you have any questions regarding the EULA, please contact us: <https://www.awingu.com/contact>

To proceed, tick the **Yes, I have read and hereby accept the above license terms and conditions** box and click *Next*.

## Step 2 - Restore Backup (optional)

Restore Backup (Optional) 2/6

ⓘ If you want to install from an environment backup, please upload one here. If you do this, the fields in the following steps will already be pre-filled with the information from the backup. You can however still adjust them if needed. Note that backups with an external database do not contain the actual data in the external database. These backups can only be used to setup a new Workspace environment against an existing and populated external database. If you want to setup a new environment from scratch, this step can be skipped.

Backup file

No file selected.

Password

Password (Optional)

If the backup is encrypted, provide the password here. Otherwise, leave blank.

Previous

Next

Finish

It is possible to restore the Awingu environment from an existing backup. Mind that you must use the same Awingu version and the same type of database.

Other settings such as IP addresses, hostnames, credentials, ... will be prefilled, but can be altered.

For more information about backups, see [Backup and recovery of the Awingu Environment](#).

For new installations, you can simply skip this step.

### Step 3 - Setup Management User

Setup Management User 3/6

ⓘ The Management User has precedence over users from your LDAP/AD Server(s). It is important to define a username which is not and will not be used on the LDAP/AD Server(s).  
 • The username cannot be changed afterwards.  
 • The password of the Management User can be changed afterwards via its Account Settings, but only when providing the previous password. A forgotten password cannot be recovered!

\* Required field

Username \*

 Username

Password \*

 Password

Confirm Password \*

 Confirm Password

Previous


Next

Finish

An Awingu environment requires a **Management User**, which is a purely administrative account.

This Management User will be able to log in at any time and alter configuration settings. After connecting Awingu to your LDAP/AD Server(s) using the [Domain Settings](#), you will also be able to add additional users with administrative privileges. Contrary to users on the LDAP/AD Server(s), this Management User will not be able to launch streamed applications or access drives. This user is not taken into account for licensing and does not require a one-time password (OTP) to sign in.

It is advised not to use this Management User, except for the installation or in case of emergency.

 The Management User has precedence over users from your LDAP/AD Server(s). It is important to define a username that is not and will not be used on the LDAP/AD Server(s). The username cannot be changed afterwards.

✖ The password of the Management User can be changed afterward via its Account Settings, but only when providing the previous password. A forgotten password cannot be recovered!

To define a management user, please populate the following fields:

- **Username:** Username of the Management User.
- **Password:** Password of the Management User.
- **Confirm Password:** Repeat the password of the Management User.

If all of the above is populated correctly, click *Next*.

#### Step 4 - Server Configuration

The installer requires the following network information:

- **Hostname:** Enter the hostname (only a-z, 0-9 and - are accepted) of the Awingu appliance. If the DHCP server is providing a hostname, it will be pre-filled.
- **DNS Servers:** Comma-separated list of IP addresses of your Domain Name System servers. Mind that we recommend using internal DNS servers.
- **NTP Server:** The IP or host of your Network Time Protocol server. It's recommended to specify 3 trustworthy NTP servers. You can use the *Active Directory* server if the time source of that server is reliable ([more information](#)).

✖ Note that the hostnames of your Awingu appliance(s) cannot be changed afterward.

If all of the above is populated correctly, click *Next*. The provided configuration settings will be evaluated and some preliminary checks will be executed:

- **DNS Servers:** the installer verifies if the given servers are DNS servers.
- **NTP Servers:** the installer performs NTP calls to the given servers.

Note that the NTP settings will be ignored if they are provided via DHCP.

#### Step 5 - Database Configuration

Optionally the Workspace allows connectivity to an external database. For a single node deployment and a multi node deployment for max. 200 users, the specification is optional. However, connectivity to an external database is mandatory in case the number of concurrent users exceeds 200 or in case high-availability is needed on the database. If you do not specify an external database, the Workspace will run an internal database.

**Warning:** Changing the database configuration from internal to external is not possible anymore after the installation.

\* Required field

☐ Enable external database

Database Protocol

Username

Password

Database Name

Database Host

Port


Optional

Previous Next Finish

Optionally Awingu allows connectivity to an **external database**.

For a single-node deployment and a multi-node deployment for max. 200 users, the specification is optional. However, connectivity to an external database is **mandatory** in case the number of concurrent users **exceeds 200** or in case **high-availability** is needed on the database.

If you do not specify an external database, Awingu will use an internal database.


 Migrating from an internal to an external database after installation is not possible.

Changing the database connection URL after installation is not possible.

When using an external database, the following properties need to be provided:

- Database Protocol: Awingu provides connectors for *Microsoft SQL (both on-premises Microsoft SQL Server as well Microsoft Azure SQL Database)* and *PostgreSQL*.
- Username
- Password
- Database Name
- Database Host: The server can be defined with its Fully Qualified Domain Name (FQDN is recommended in case the IPv4 address ever changes) or its IPv4 address.
- Port (optional)
- Database Instance Name (optional): In the case of named instances (Microsoft SQL Server), a database instance name can be provided.

Please make sure the specified account and database are available before proceeding.

 When using the connector for **Microsoft SQL**, make sure the following database properties are switched on:

- READ\_COMMITTED\_SNAPSHOT
- ALLOW\_SNAPSHOT\_ISOLATION

You can do so by running these SQL queries (replace 'awingudb' with your own database name):

```
ALTER DATABASE awingudb SET allow_snapshot_isolation ON;
ALTER DATABASE awingudb SET SINGLE_USER WITH ROLLBACK IMMEDIATE;
ALTER DATABASE awingudb SET read_committed_snapshot ON;
ALTER DATABASE awingudb SET MULTI_USER;
```

When using the connector for **PostgreSQL**, make sure the password authentication method is not set to SCRAM.

If the required database properties are filled in, click **Next**. The connection to the database will be verified by creating, editing and deleting a table in the database. We also check if the database is not already in use by Awingu.



### Supported External Databases

- Microsoft Azure SQL Database (v12.0)
- Microsoft SQL Server 2019 (v15.0) and 2022 (v16.0) - only for Microsoft Windows.
- PostgreSQL v9.4 and higher

## Step 6 - Summary

Summary 6/6

Management User Credentials

Username

admin

Password

\*\*\*\*\*

Server Configuration

Hostname

awingu

DNS Server

8.8.8.8

NTP Server

pool.ntp.org

Previous

Next

Finish

All required configuration parameters are now provided and can be verified on this page. Click on *Finish* to start the installation process


### Installation Progress

The Awingu appliance is ***installing packages***.

This operation will take ***approximately 15 min***.

When the installation is completed, you will be presented with a sign-in screen.

### Install complete



***The installation is complete.***

You can sign in using your **Management User** credentials provided in [step 3](#) and start configuring your Awingu platform using [System Settings](#).

⊗ Note that the session of the **Management User** expires after 15 minutes and you will need to log in again.

The next configuration steps are:

1. Creating a first domain in [Domain Settings](#)
2. Defining an admin group in [User Connector Configuration](#)

When done, you will be able to use an AD user who is a member of this specified admin group to log in to Awingu. This is recommended.



# Azure Awingu All-In-One

- [Introduction](#)
- [Deployment](#)
  - [Basics](#)
  - [Awingu Configuration](#)
  - [Windows Backend Configuration](#)
  - [Summary](#)
- [Next Steps](#)

## Introduction

The *Awingu All-In-One* Azure marketplace solution allows you not only to deploy an Awingu appliance, but also to deploy a complete Windows backend infrastructure and configure Awingu to use this backend. The result of an *Awingu All-In-One* Azure marketplace solution is a pre-configured, ready-to-use Awingu environment hosted in the cloud.

This might be useful in following scenarios:


- Greenfield projects where no existing Windows environment is available
- Migration to the cloud
- Testing purposes, e.g. to evaluate Awingu


## Deployment


Deploying an *Awingu All-In-One* Azure marketplace solution is done through the Azure Portal using a wizard in 3 easy steps.

To start the wizard, search for 'Awingu All-In-One' on the Azure marketplace and click the 'Create' button.

The wizard will present you some options and questions in easy 3 steps.

 Please note that *Awingu All-In-One* is not available in Azure Classic.





## Basics

The first step 'Basics' covers Azure settings and determines where your *Awingu All-In-One* environment will be deployed.

This is based on the Azure subscription and datacenter selected. All virtual machines will be deployed in a single, newly created *Resource Group*.

**i** Currently it is only possible to deploy in a new Resource Group.

Microsoft Azure

Create Awingu (Staged) > Basics

1 Basics  
Configure basic settings

2 Awingu  
Configure Awingu

3 Windows Backend  
Configure Windows Backend

4 Summary  
Awingu (Staged)

5 Buy

Subscription  
BizSpark Plus

\* Resource group ⓘ  
Create new  
My-Awingu-All-In-One ✓

Location  
West Europe

OK

## Awingu Configuration

The second step 'Awingu Configuration' will present you with all options and questions required to deploy and configure the Awingu appliance.

Microsoft Azure

Create Awingu (Staged) > Awingu Configuration

1 Basics  
Done ✓

2 Awingu  
Configure Awingu

3 Windows Backend  
Configure Windows Backend

4 Summary  
Awingu (Staged)

5 Buy

\* Email address ⓘ  
doc@awingu.com ✓

\* Public IP address ⓘ  
(new) Awingu

\* DNS prefix ⓘ  
my-awingu-aio ✓  
westeurope.cloudapp.azure.com

\* Awingu recovery password ⓘ  
\*\*\*\*\* ✓

\* Confirm password  
\*\*\*\*\* ✓

\* Awingu appliance size  
1x Standard F2

OK

Label	Description
Email address	Your email address to provide you with access to documentation and support. You will receive links and information on this address.
Public IP address	Public IP address on which your Awingu environment will be accessible from the internet.
DNS prefix	DNS prefix for the Awingu environment. You will be able to access your Awingu environment on {prefix}.{location}.cloudapp.azure.com.
Awingu recovery password	This password allows you to recover your Awingu environment in case of backend problems.
Awingu appliance size	Azure appliance size to use for the Awingu appliance.

## Windows Backend Configuration

The third step 'Windows Backend Configuration' will present you with all options and questions required to deploy and configure the Windows backend servers.

This backend will consist of 1 Active Directory server and a selectable amount of Windows application servers. The Awingu appliance will be configured automatically to connect to these servers.


Label	Description
Admin username	Admin username for Awingu and Windows backend. This username will be domain administrator on the Windows backend.
Admin password	Admin password for Awingu and Windows backend.
Domain name	Windows domain name used for the Windows backend. (FQDN)
Application server count	Specify the number of application servers you want to deploy. These servers will host the Windows applications. The number of servers depends on the expected load. Servers can always be deployed later on and easily imported in Awingu.
Windows	Azure appliance size to use for all Windows servers.

server size

## Summary

This step gives you a summary of earlier provided information for review.

If all information is correct, press OK to start deploying your *Awingu All-In-One* environment.



## Next Steps

Congratulations! You have your *Awingu All-In-One* environment up-and-running!

Now you can navigate to <http://{prefix}-{location}.cloudapp.azure.com> and sign-in using the admin username and password provided in step 2 of the wizard.

# System Settings

- [Introduction](#)
- [Multi-tenancy](#)

## Introduction

An Awingu environment can be installed via a web based installer. Once the installation has been finalized, the System Settings can be used to change and apply new parameters, adding applications, drives, etc.

The first time you login, you can use your **Management User** credentials provided during installation.

✖ Note that the session of the **Management User** expires after 15 minutes and you will need to login again.

The next configuration steps are:

1. Creating a first domain in [Domain Settings](#)
2. Defining an admin group in [User Connector Configuration](#)

When done, you will be able to use an AD user who's a member of the admin group to login to Awingu. This is recommended.

## Multi-tenancy

The Awingu solution supports multi-tenancy for end-users and segregated access to the management interface:

- **Domain Admins** can only manage their specific settings.  
A Domain Admin is a user which is member of a security group labeled as *admin* user in the [User Connector](#) of a domain **not** marked as an *Administrative Domain*, as configured in [Domain Settings](#).
- The **Management User** and **Global Admins** can manage all domains and generic settings. In the top left corner, the user can toggle between domains. The generic settings are in the Global menu in the top right corner.
  - The Management User is the user defined during installation.
  - A Global Admin is a user which is member of a security group labeled as *admin* user in the [User Connector](#) of a domain marked as an *Administrative Domain*, as configured in [Domain Settings](#).

More information can be found in the section [Service Provider Support in Awingu](#).

## System Settings - Global

The Global section hosts a number of pages which are only accessible by the Management User or the Global Admins.


- [Connectivity Settings](#)
- [General Information](#)
- [Service Management Settings](#)
- [Domain Settings](#)
- [SSL Offloading Settings](#)
- [Troubleshoot](#)

## Connectivity Settings

- [Servers](#)
- [HTTP Proxy](#)
- [External Reverse Proxy](#)
- [SNMP](#)
- [Environment Backups](#)
- [Vault](#)

The connectivity section groups parameters required for Awingu to interface with external services.

### Servers



The screenshot shows the 'Connectivity Information' page in the Awingu interface. The 'Servers' section is active, displaying the following configuration:


Parameter	Value	Action
NTP Server(s)	dev-awingu-ad1.dev-awingu.com,dev-awingu-ad2.dev-awingu.com	Edit
DNS IP Address(es)	172.16.0.25,172.16.0.26	Edit
Repo Server URL	http://notbuild.awingu.com	Edit

The footer of the interface indicates 'System Settings - © 2012-2018 Awingu N.V. - Eula' and the version '4.1'.

The servers are configured during the installation and can be edited here.

- **NTP server:** The IP or fully qualified domain name of your **Network Time Protocol** server. You can use the *Active Directory* server if the time source of that server is reliable ([more information](#)). It's recommended to specify 3 trustworthy NTP servers. Note that the NTP settings will be ignored if they are provided via DHCP.
- **DNS IP address(es):** IP address(es) of one or more DNS servers to be used by Awingu.
- **Repo Server URL:** The repo server hosting the Awingu software (needed for upgrades). Please fill in the following URL: <https://repo-pub.awingu.com>.

### HTTP Proxy



The screenshot shows the 'HTTP Proxy' configuration page. The 'State' is set to 'Disabled' (indicated by a blue radio button). The 'HTTP Proxy Server URL' field is empty. There are 'Cancel' and 'Apply' buttons at the bottom right. The footer of the interface indicates 'System Settings - © 2012-2018 Awingu N.V. - Eula' and the version '4.1'.

The HTTP Forward Proxy server is configured during the installation and can be edited here. The proxy server will be used to reach public services, like the Repo Server of the previous section, DUO MFA and OneDrive. Note that automatic SSL (Let's Encrypt) is not using this proxy. Please refer to [Connectivity Requirements](#) for more details about outbound connections.

- **State:** Enable or Disable the use of an HTTP Proxy Server
- **HTTP Proxy Server URL:** The URL of an HTTP forward proxy server. Username and password can be embedded in the URL, e.g. <http://username:password@proxy.mycompany.com>

### External Reverse Proxy



DEV-AWINGU
Configure
Manage
Changes
Global

## External Reverse Proxy

Reverse Proxy IPs

When using Awingu behind an external reverse proxy, load balancer or SSL offloader, enter their IPv4 address(es) or network(s) (comma separated). For requests that come from these IPs, we will use the supplied client IP in the X-Forwarded-For or X-Real-IP headers. Otherwise we will use the actual IP that was used to connect to Awingu as the client IP. The correctness of this client IP is important for auditing and whitelisting purposes.

If you are accessing Awingu without reverse proxy, load balancer or SSL offloader, please keep this field empty for security reasons.

Cancel
Apply


System Settings - © 2012-2018 Awingu N.V. - Eula
4.1

Relevant when using Awingu behind an external reverse proxy, load balancer or SSL offloader. Here you specify their IPv4 address(es) or network(s) (comma separated). For requests that come from these IPs, Awingu will use the supplied **client IP** in the **X-Forwarded-For** or **X-Real-IP headers**. Otherwise we will use the actual IP that was used to connect to Awingu as the client IP. The correctness of this client IP is important for auditing and whitelisting purposes.

If you are accessing Awingu without reverse proxy, load balancer or SSL offloader, please keep this field empty for security reasons.

### SNMP

SNMP

State	Enabled	
Username	snmp	
Password	*****	

The status and health of Awingu appliances can be monitored and integrated in your monitoring system using SNMP. If enabled, all Awingu appliances provide an SNMP agent which is accessible using SNMPv3. All communication is AES *encrypted* and access is *password protected*. The agents are accessible on *UDP port 161* with the read-only user awingu.

- **State:** Enable or Disable SNMP agents on the Awingu appliance(s)
- **Username:** Read-only user *awingu* or *snmp* (5.0.2 and later). The username depends on the version of Awingu.
- **Password:** Self-selected password required to access the SNMP agents

An example of a snmpwalk command (for Linux users):

```
snmpwalk -v 3 -Os -l authPriv -u <awingu or snmp> -x AES -X '<password>' -a SHA -A '<password>' <appliance IP>
```

### Trusted Certificate Authorities

## Trusted Certificate Authorities

### Global certificate

No file chosen

Certificates can be added which are used to verify the server identity when making HTTPS requests (e.g. connections to the repo server, external audit logging server, Reverse Proxied Web applications, HTTP proxy,...).


Certificates can also be added per Domain, see the Domain Details. To add multiple global certificates, they will need to be bundled into one file.

It's possible to add globally trusted certificate authorities. These will be trusted by all configured Awingu domains.

Certificates can be added which are used to verify the server identity when making HTTPS requests (e.g. connections to the repo server, external audit logging server, Reverse Proxied Web applications, or HTTP proxy). Certificates can also be added per Domain. For more information, see the Domain Details. If you want to add multiple global certificates, you will need to bundle them into one file.

This can be done by copy-pasting the content of each PEM certificate (.pem/.cer/.crt) into one PEM file using any basic text editor.

## Database connection



Optionally Awingu allows connectivity to an **external database**. This setting is configured during the [installation](#) and cannot be edited afterwards.

## Environment Backups

### Environment Backups

SFTP Username	dbbackup	
SFTP Password	*****	<input type="button" value="Edit"/>
Encryption Password	Not set	<input type="button" value="Edit"/>
Vault Backups	Disabled	<input type="button" value="Edit"/>
Start backup at	23:45:00	<input type="button" value="Edit"/>

Awingu creates a backup of the environment every day and stores it on the appliance. You can retrieve this backup and save it on another system via SFTP. The backups are retained on the local disk for a period of 3 days, before being discarded. More information: [Backup and recovery of the Awingu Environment](#).

You can choose the credentials of the SFTP user that can access the backup files:

- **SFTP Username:** SFTP username *dbbackup*. This cannot be changed.
- **SFTP Password:** SFTP password.
- **Encryption Password:** Password to use to encrypt the environment backups. We highly recommend setting a password, since backups may contain sensitive information. When this password is not set, backups will not be encrypted. Encrypted backups have the '.enc' extension and will require this same password to be able to restore the backup.
- **Vault Backups:** Determines whether the vault is also backed up.
- **Start backup at:** Schedules the time of the daily backup.

## Vault

The vault is needed when you want to [enable Single Sign-On](#) in Awingu.

Since the private key for the Awingu SubCA allows Awingu to impersonate Windows users, this key is highly sensitive and is stored in a vault inside Awingu. The vault itself is also encrypted and the encryption key for the vault can either be stored on the Awingu appliance itself (Internally) or on an external Vault provider like Google Cloud Key Management Service or Azure Key Vault.

For more details see [Enabling Single Sign-On \(SSO\)](#)

## General Information

- [License](#)
- [Management User](#)
- [Remote Support](#)
- [Anonymous Usage Reporting](#)
- [System Message](#)
- [Upgrade Version](#)
- [Migrate Audit Logs](#)
- [Partner](#)
- [Account Manager](#)

### License

This section allows you to upload your Awingu license key and displays key information regarding your license. If a license key is in use, and you upload a new key, the previous key gets overwritten. There is only one active key at any point in time.

**i** The Management User can always sign-in to Awingu, even when the user limit or the expiration date has been reached.

### Management User

The management user can log into the System Settings even when Awingu's connectivity to the authentication service has not yet been established. For more information, please refer to [the appropriate section of the Awingu installer](#).

- **Username:** Username of the management user (**cannot** be edited).
- **Whitelisted Subnets:** If enabled, you can only login with the management user from the provided list of subnets. A typical use case is to only allow access from within the company or the data center.

In order to change the password of the management user:

- Login with the username and password of that management user. When OTP or Radius is enabled, you don't need to provide any token.
- In the bottom left, click on the profile menu and select **Account settings**.
- Click on **Change password**.

### Remote Support

Some interventions by the Awingu Support Team require SSH access. When temporarily opening the SSH port (TCP:22) on your firewall for the intervention, it is recommended to use an intervention password that you can communicate to the Support Team as an additional layer of security. If you don't enable this feature, the Support Team will be able to access your environment without an intervention password.

When you enable the **Intervention Password** a password will be generated for you.

## Generate Intervention Password

Are you sure you want to generate a new intervention password? This will replace any previous intervention passwords. Please don't lose the generated intervention password! Without the password, you cannot get any remote support from the Awingu Support Team anymore.

Cancel

Confirm

## Intervention Password

Your new intervention password is:

xs9DqfteG6t

**Important:** this password will not be shown again. Do not lose it! Without it the Awingu Support Team will not be able to login to your appliances for interventions.

Close

At any point in time you can regenerate the intervention password.

#### Anonymous Usage Reporting

When enabled, the appliance will periodically send anonymised usage data to Awingu. The data does not include any identifiable references, such as names of users, groups, applications etc.

This feature requires your Awingu appliance to have access to <https://analytics.awingu.com> and can be enabled or disabled at any point in time.

#### System Message

This feature allows an administrator to send a message to all users of the Awingu environment.

- This message will appear maximum 5 minutes after the message is set and will be shown at the top of their page (see screenshot below). The user can close the message but it will re-appear again after login.
- The message supports HTML which can be useful if you want to add a link with more information.



#### Upgrade Version

When a new version of Awingu is published, the version will be shown in the drop-down list if the Awingu appliance is entitled to the upgrade.

For this to happen, there needs to be an active support contract (license) to obtain the latest version. If the most recent version is missing, keep in mind that Awingu may require intermediate upgrades before you see the latest version. The Awingu appliance must also be able to connect to our update repositories.

To upgrade to a new version, the packages need to be **downloaded** first. You cannot upgrade to any version or download other versions while the download is happening.

When clicking Upgrade, the minimum hardware requirements will be validated. See [Sizing & Scaling Requirements](#) for more information.

Before **each** upgrade, we highly recommend taking a **backup or snapshot of your Awingu node(s)**. If applicable: do not forget to take a snapshot/backup of your **external database** as well.

#### Migrate Audit Logs

 This section is only available on environments that upgraded to Awingu 5.0 and did not yet migrate their logs to the database.

Starting from Awingu 5.0 audit logs are also stored in the database. This section allows you to migrate your existing audit logs to the database. **This will be required to upgrade to Awingu 5.1**

To start the migration process, click on the 'Start Migration' button.

We strongly advise taking a snapshot prior to performing this operation.

#### Partner

Enter the contact details of the **partner** which is responsible for installation and upgrades of the Awingu platform.

- **Name:** Name of the partner.
- **Address line 1:** Address of the partner.
- **Address line 2:** Address of the partner. (*optional*)
- **Zip or Postal code:** Zip code.
- **City:** City.
- **Location:** state/province/region.
- **Country:** Country.
- **Phone:** Phone number of the partner. (*optional*)

#### Account Manager

Enter the contact details of the **account manager**, the prime contact person at your **partner**.

- **Name:** Name of your contact person.
- **Phone Number:** Phone number of contact person. (*optional*)

## Service Management Settings

- [Introduction](#)
- [Application Sessions Failover](#)
- [Services](#)
- [Adding Awingu appliances](#)
- [Removing an Awingu appliance](#)
- [Assigning roles](#)

### Introduction

Service Management enables you to add and remove Awingu appliances (nodes) to your environment, define the roles of each Awingu appliance and configure Application Sessions Failover.

The main page gives you an overview of all registered Awingu appliances and which roles are assigned to them.

Please refer to [Sizing & Scaling Requirements](#) for supported multi-node architectures.



#### Remarks


Once an appliance has been added and configured, **you cannot change its IP address**. Doing so will result in services failing.

To be able to change IP addresses in a multi-node setup, the Awingu environment first needs to be scaled down to a single-node.


(1) Multi-node (2) Remove all other nodes (3) Change IP of the single-node (4) Add new nodes (old nodes can be deleted)

### Service Management


#### Application Sessions Failover

State Enabled 

#### Services

 Appliances can only be deleted if no service are assigned to it.  
The database service cannot be moved when an internal database is used.  
Adding and removing appliances, and (un)assigning services will result in service interruption (exception: adding an appliance with only the frontend service).

Hostname	IP Address	Database	Backend	Frontend
nightly-install-4-2	172.16.4.6	✓	✓	✓



### Application Sessions Failover

This feature determines the behavior when an Awingu node would fail.

- If enabled, Awingu will redistribute all existing application sessions that are actively connected to a user of the failing node to the other available Awingu nodes. Users will not lose their application session and can continue to work after a few seconds.
- If disabled, all existing application sessions on that failing node will be lost. Users will need to restart their applications.

### Services

Selecting an appliance from the list will show its details below the list.

You can modify your environment by clicking the edit button.


#### Adding Awingu appliances

1. Make sure all TCP, UDP and ICMP network traffic is allowed between all Awingu appliances. The appliances should have the same version as the existing Awingu environment.
2. Click on the pencil next to the table.
3. Click on **Add appliance**.
4. After a maximum of 10 seconds, the **Discovered Appliances** section will show a list of all Awingu appliances in the network. Discovery of appliances only works when broadcasting is allowed on the network. This is usually not the case on public clouds.
5. When using discovery: click on a discovered appliance, change its hostname if desired, and click on **Add**.  
When not using discovery: fill in a hostname and an IP address in the form at the bottom and click on **Add**.
6. Check the roles you want to assign to the new appliance (see further).
7. Repeat steps 3-6 for all appliances.
8. Click on **Update**.

#### Removing an Awingu appliance

In order to remove an Awingu appliance:

1. Click on the pencil next to the table.
2. Uncheck all roles that were assigned to the appliance.
3. Delete the appliance from the list.
4. Click on **Update**.

 If the appliance was still running, Awingu will try to shut it down. **Do not start that appliance again!**

#### Assigning roles

To assign a role to an Awingu appliance, make sure the corresponding role is ticked for the appliance.

Click **Update** to apply the configuration changes.

In case the update fails due to e.g. system inconsistencies, you can check the option **Ignore operational errors** to continue despite these warnings.

Please consider that this might break your environment! It is recommended to contact the Awingu support team through <https://my.awingu.com>

The following roles are defined:

- **Database:** Provides the database service to store all metadata. This role cannot be moved. This role is not present when using an external database.
- **Backend:** Provides all services required for the internal operation of the Awingu platform (indexer, metering, mq). One appliance with a backend role is enough to serve thousands of concurrent users. For high availability (HA), 3 appliances are required.
- **Frontend:** Provides all APIs and brokering services (frontend, memcache, proxy, rdpgw, worker). This role scales horizontally and is CPU bound.

 Always make sure that the **backend** role is assigned to 1 appliance (non-HA) or 3 appliances (HA).

## Domain Settings

- [Introduction](#)
- [Domains](#)
- [Default Domain](#)











### Introduction

Awingu does not store user credentials, but instead authenticates and authorizes users based on information retrieved from the existing enterprise authentication and authorization infrastructure. This approach avoids the need to maintain user credentials in several systems and allows keeping user data in a central location. It also speeds up the roll-out of Awingu as there is no need to configure users in the Awingu platform.





### Domains

## Domains

Bulk Action ▾





✓	Name ▴	NetBIOS Nam...	Domain FQDN...	Administrativ...	Is Default	Actions
✓	DEV2016	DEV2016	dev2016.dev-a...	✓		Set default  
✓	DEV-AWINGU	DEV-AWINGU	dev-awingu.com	✓	✓	Set default  
✓	FEATURES	DEV-AWINGU	dev-awingu.com			Set default  
✓	OFFICE365	DEV-AWINGU	dev-awingu.com			Set default  
✓	OTP	DEV-AWINGU	dev-awingu.com			Set default  

Items per page 10 ▾

  1 / 1  

Add

Domains can be added using the [Add] button, or modified by clicking the pencil button in the [Actions] column of the selected domain.

Domain Details	
Name	DEV-AWINGU
Host Headers	dev-awingu.com 
Administrative Domain?	Yes 
Max Licensed Users	Disabled 
Privacy Policy Acceptance	Disabled 

A *domain* is defined by the following properties:


- **Name:** Domain name used in Awingu. Multiple names can refer to the same NetBIOS name.




- **Host Headers:** In case of having multiple domains: when reaching Awingu via one of the host headers defined here, the branding of this domain will be used and the domain does not need to be filled in (the extra field to enter a domain will be hidden at the login page). Multiple host headers can be entered comma separated.
- **Administrative Domain:** When set to yes, admin users of this domain are allowed to configure all domains, global settings and have access to the Dashboard. Admin users can be defined in [User Connector Configuration](#).
- **Max Licensed Users:** If enabled, you can configure the maximum number of concurrent or named (depending on the license) users that are allowed to be logged in to this domain. When set to 0, domain users can't access the domain anymore.
- **Privacy Policy Acceptance:** When set to enabled, each user will have to accept the Privacy Policy the first time they log in. This is needed for GDPR compliance.


Connectivity		
NetBIOS Name	DEV-AWINGU	
Domain FQDN	dev-awingu.com	
DC/LDAP Server	dev-awingu-ad1.dev-awingu.com,dev-awingu-ad2.dev-awingu.com	
Base DN	dc=dev-awingu,dc=com	
LDAP over SSL?	Enabled	
DNS Servers	172.16.0.25,172.16.0.26	

- **NetBIOS Domain Name:** NETBIOS domain name (e.g. MYCOMPANY)
- **Domain FQDN:** The FQDN of the (Active Directory) domain. E.g. domain.internal
- **DC/LDAP server:** It is highly recommended to specify the FQDN of the Domain Controller or LDAP server, especially when planning to move to Single Sign-On (SSO) at some point. E.g. ad01.domain.internal. Alternatively, you can use IP addresses. Do not simply point to the FQDN of the Windows domain. Multiple servers can be entered comma separated. The first server will always be contacted as the first one during login. If there is no connectivity to the first server, Awingu moves on to the next one on the list.
- **Base DN:** When a user signs in, this base distinguished name (DN) is used to bind via LDAP to the Domain Controller/LDAP server. This can be used to filter access based on organizational unit (OU).  
Example without OU restriction: dc=domain,dc=internal  
Example with OU restriction: ou=Employees,dc=domain,dc=internal

 This field can be used to create different Awingu domains, all pointing to the same NetBIOS. Only users of the configured OU will be able to log in to that domain.

- **LDAP over SSL?:** Requires SSL certificate on Domain Controller or LDAP Server.

 LDAP over SSL is required to allow users to change their password via Awingu. Note that Microsoft advises using LDAPS on domain controllers.

 Please make sure the SSL certificate installed on the AD/LDAP server for LDAPS is encrypted using **SHA256**. A certificate using SHA512 is NOT supported by Awingu. Therefore, LDAPS login will not work with SHA512.

- **DNS Servers:** This DNS server is used to resolve servers matching the domain FQDN. Multiple servers can be entered comma separated. E.g. if the domain FQDN is domain.internal, then fileserver.domain.internal will be resolved with the mentioned DNS server.

Bind user		
Bind user for domain	bsyncer #&%	
Password for bind user	*****	
Functions		
Create Bind Name	builtin.create_domain_bind_name	
Find Groups	builtin.find_groups_by_token_groups	

Optionally, a service user account can be defined which is required for importing labels (users and groups) and applications servers from Active Directory from within System Settings. This is also required to enable single sign-on (SSO). To configure this service account, the following parameters are required:

- **Bind user for domain:** The username of the service account.
- **Password for bind user:** The password required to authenticate the service account.

For security reasons, it is recommended to create a new read-only user account with limited rights on the Domain Controller/LDAP Server for this purpose only.  
Note that the "Base DN" is not used during the import, meaning that domain admins will be able to see all users/groups/servers of the whole Windows domain, unless the bind user has been configured on the Active Directory to only allow to list the ones of its OU.

Some advanced functionality:

- **Create Bind Name:** defines how to bind user names in LDAP:
  - builtin.create\_domain\_bind\_name (default): bind to LDAP via "DOMAIN\username"
  - builtin.create\_username\_bind\_name: bind to LDAP only via the username
  - builtin.create\_uid\_bind\_name: bind via uid=<username>,ou=Users,<base dn>
- **Find Groups:** defines how to query the LDAP Server for groups to which a user belongs.
  - builtin.find\_groups\_by\_member\_of: find group via memberOf field in LDAP result
  - builtin.find\_groups\_by\_token\_groups (default): find group recursively (method 1) Note: this method also fetches the primary group attribute.
  - builtin.find\_groups\_by\_member: find group recursively (method 2).
  - builtin.find\_groups\_by\_uid: find group via UID.

Trust settings		
Trusted Certificate Authorities	<input type="button" value="Choose File"/> No file chosen	<input type="button" value="Show Certificate"/>
Certificates can be added per domain which are used to verify the server identity when making HTTPS requests (e.g. external audit logging server, Reverse Proxied Web applications, ...). Certificates can also be added on a Global level, see Connectivity > Global Certificates. To add multiple Domain certificates, they will need to be bundled into one file.		
		<input type="button" value="Cancel"/> <input type="button" value="Apply"/>
<b>Allow untrusted servers</b> Determine if connections can be made to untrusted servers for the following features.		
External Audit Logging	Block untrusted	
Reverse Proxied Web Applications	Block untrusted	
WebDav with SSL	Block untrusted	
Pre-auth/SSO metadata	Block untrusted	

The Trust settings make it possible to specify domain-specific trusted certificate authorities.

- **Trusted Certificate Authorities:** Certificates can be added per domain. They are used to verify the server identity when making HTTPS requests (e.g. external audit logging server or Reverse Proxied Web applications). Certificates can also be added on a Global level, see Connectivity > Global Certificates. If you want to add multiple domain certificates, you will need to bundle into one file. This can be done by copy-pasting the content of each PEM certificate (.pem/.cer/.crt) into one PEM file using any basic text editor.
- **Allow untrusted servers:** Determine if connections can be made to untrusted servers for each of the following features:
  - **External Audit Logging**
  - **Reverse Proxied Web Applications**
  - **WebDav with SSL**
  - **Pre-auth/SSO metadata**

#### Default Domain

A default domain is configured, which will be used if no domain is specified at login time or no correct host header was used. To change the default domain, use the set default action on the domain to use as default.

## SSL Offloading Settings

- [Introduction](#)
- [SSL Offloader](#)
- [Generating certificates automatically](#)
- [Uploading certificates manually](#)
  - [PKCS 12 certificates](#)
  - [PEM certificates](#)
    - [PEM Certificates with passphrases](#)
    - [Self-Signed Certificates](#)
- [Certificate content](#)
- [Replacing and deleting certificates](#)



### Introduction

If no external SSL offloader is available, Awingu can handle the SSL offloading (also referred to as SSL termination) internally.

When using multiple Awingu nodes for high availability reasons, we recommend using an external SSL offloader.

Only when the internal SSL offloader is used, you need to upload or generate the certificates in Awingu via **Global > Certificates**.

Once the first certificate is uploaded or generated, Awingu will start serving HTTPS on port 443. To enforce HTTPS, please refer to [Connectivity Settings](#).

### SSL Offloader

If no external SSL offloader is available, Awingu can handle the SSL offloading (also referred to as *SSL termination*) internally.

When using multiple Awingu nodes for high availability reasons, we recommend using an external SSL offloader.

In [Certificate Settings](#), you can upload or generate SSL certificates. Once the first certificate is added, Awingu will start serving HTTPS on port 443.

The internal SSL offloader can be used in three states:

- **Optional HTTPS:**
  - If you don't use an external SSL offloader, Awingu is accessible via both port 80 (HTTP) and 443 (HTTPS). When accessing via HTTPS, the session cookies have the secure flag enabled: your session cookie is only valid for future HTTPS connections.
  - If you use an external SSL offloader, you will typically not have certificates uploaded in Awingu and the SSL offloader will access Awingu through port 80.
- **Internal SSL offloading with enforced HTTPS:**
  - You are not using an external SSL offloader.
  - Awingu is only accessible via port 443 (HTTPS). All traffic on port 80 (HTTP) will be redirected to 443.
  - The session cookies have the secure flag enabled: your session cookie is only valid for future HTTPS connections.
- **External SSL offloading with enforced HTTPS:**
  - You are using an external SSL offloader.
  - You will typically not have certificates uploaded in Awingu and the SSL offloader will access Awingu through port 80.
  - The session cookies have the secure flag enabled: your session cookie is only valid for future HTTPS connections.

**i** Enforced HTTPS with internal or external SSL offloader can only be selected when accessing the System Settings via HTTPS. This is to avoid being locked out of Awingu.  
Note: if you switch back from HTTPS to HTTP, you will need to clear your browser cache and delete your Awingu cookies to be able to use Awingu again.

When HTTPS is enforced (either internally or externally) the option to enable the **HSTS header** will become available.

Enabling this header will inform the browser that the Workspace should only be accessed using HTTPS, and that any future attempts to access it using HTTP should automatically be converted to HTTPS.

This header can be configured using the following options:

- **Max Age:** The time, in seconds, that the browser should remember that the Workspace is only accessible when using HTTPS.
- **Include Subdomains:** Determines if the HSTS header is also active on all of the website's subdomains.
- **Preload:** When enabled, the Workspace URL can be submitted to the HSTS preload list. To be accepted to the list, other requirements also need to be met.

It is recommended to increase the Max Age in stages e.g. starting with 5 minutes and gradually increasing this to a maximum of 2 years while monitoring the Workspace for issues.

More information on how to add your Workspace URL to the HSTS preload list can be found here: <https://hstspreload.org/>

When HSTS was previously enabled and the Max Age is not yet expired when switching back to Optional HTTPS, the Workspace will become inaccessible.

Clearing the Workspace browser data (including the HSTS settings) or using a different browser will make the Workspace accessible again.

#### Generating certificates automatically

If you do not own SSL certificates, you can use the *Automatic* option which will generate and configure SSL certificates provided by the free CA service of <https://letsencrypt.org>

To generate certificates automatically, click on Add and provide following information:

- **Certificate:** Automatic
- **Subject Names:** the host name(s) you want to create certificates for (e.g. [awingu.mycompany.com](https://awingu.mycompany.com))

The generated certificates are valid for 90 days. After 60 days, Awingu will renew the certificate. Therefore, the public servers of Let's Encrypt always need to be able to reach the Awingu appliance on port 80 and 443.



Following network requirements are needed in order to request and renew automatic certificates:

- Ports 80 and 443 of Awingu need to be accessible for the **public** servers of Let's Encrypt through all provided subject names.
- Awingu needs to be able to reach the REST API of Let's Encrypt directly (without the use of an HTTP proxy) through port 443 for [\\*.api.letsencrypt.org](https://api.letsencrypt.org).

Please note there is a rate limit of the number certificates per registered domains and the number of duplicate certificates. Those limits are described in [the documentation of Let's Encrypt](#). You can hit this limit easily if you use a subdomain of a service or cloud provider, like [\\*.azure.com](#). Please use a subdomain you fully control.

Automatic SSL is only available for single node Awingu configuration or for multi node Awingu with only one Frontend service. Requesting wildcard certificates is currently not supported.

#### Uploading certificates manually

Awingu supports 2 types of certificates:

- PKCS 12 certificates - typically with `.p12` or `.pfx` extension
- PEM certificates - typically with `.pem`, `.crt` or `.cer` extension

#### PKCS 12 certificates



PFX files can contain multiple certificates and can be password protected.

Click on Add and provide the following information:

- **Certificate Type:** Manual PKCS 12
- **File:** The certificate file in `.p12` or `.pfx` format
- **Password (optional):** The password required to decode the certificate

#### PEM certificates

Add Certificate

Certificate Type

☐ Automatic

☐ Manual PKCS 12 (\*.p12 or \*.pfx)

☒ Manual PEM (\*.pem, \*.crt or \*.cer)

Certificate

Choose File

No file chosen

Show Certificate

Certificate is required

Private Key

Choose File

No file chosen

Private Key is required

Cancel

Add

Click on Add and provide the following information:

- **Certificate Type:** Manual PEM
- **Certificate:** The public certificate file in **.crt, .pem or cer format**, ASCII file, starting with:

```
-----BEGIN CERTIFICATE-----
```

Make sure the certificate also contains the **intermediate key chain**, otherwise some browsers might not connect to Awingu because the connection is not trusted.

- **Private Key:** The private key file associated with the certificate in **.key format**, ASCII file, starting with:

```
-----BEGIN PRIVATE KEY-----
```

or

```
-----BEGIN RSA PRIVATE KEY-----
```

#### PEM Certificates with passphrases

If you open the certificate key file and see binary characters instead of the BEGIN (RSA) PRIVATE KEY header, this means your certificate key is still encrypted with a passphrase. The Awingu SSL offloader cannot start automatically when the private key is still encrypted using a passphrase. Therefore you'll need to remove the passphrase from the private key first before uploading the key file. You can remove the passphrase by using the openssl command as follows (you will also be prompted to type in your passphrase):

```
openssl rsa -in encrypted.key -out decrypted.key
```

#### Self-Signed Certificates

Although not recommended, Awingu also supports self-signed certificates. Using self-signed certificates will show a security warning when accessing the site. They can be created for free. One of the easiest ways to do so, is to use an online self-signed certificate generator (for example: <https://en.rakko.tools/tools/46/> ).

#### Certificate content

To validate if your certificate is correct - e.g. you want to make sure the certificate contains the intermediate key chain, you can visualize the certificate's content using the **Show Certificate** button.

#### Replacing and deleting certificates

When you want to replace a certificate, e.g. because the existing one will expire soon, you first upload the new certificate and then delete the old one.



Expired manual certificates are not automatically deleted and are still offered to the browsers, which will cause a security warning for the user.

If you are deleting the last certificate of the subject name you are now browsing to, you will need to go manually to HTTP (if HTTPS is not enforced in [Connectivity Settings](#)) after deletion. If HTTPS is enforced, you need to go to another subject name you still have a certificate for. You won't be able to delete the last certificate if HTTPS is enforced, to avoid that you cannot reach Awingu anymore.

## Troubleshoot

- [Actions](#)
  - [dig](#)
  - [download-logs](#)
  - [environment](#)
  - [ip-address-appliances](#)
  - [ldapsearch](#)
  - [ping](#)
  - [shutdown-appliances](#)
  - [sync-appliances-time](#)
  - [tcpscan](#)
  - [traceroute](#)
  - [udpscan](#)
  - [uptime](#)
- [Logging](#)

## Troubleshoot

### 1. Select Action

dig  
download-logs  
environment-backup-create  
environment-backup-list  
environment-backup-restore  
ip-address-appliances  
ldapsearch  
ping

Action selection required

### 2. Execute Action

ClearSelect

Execute

## Actions

The troubleshoot page offers some tools to allow you to manage internal database backups and to troubleshoot why your configuration is not working as expected.

The steps are as follows:

1. Select Action:
  - Select a troubleshoot action to execute
  - Some actions need arguments. Please enter them.
2. Select Target Appliance(s) to execute an action on
3. Execute Action:
  - Execute: execute the selected action and the output will be shown in the text box
  - Clear: empty the output text box
  - Select: select all output in the output text box

✖ All actions executed on the Troubleshoot page are logged into the log files. If you enter passwords in the commands, they will be logged in plain text. Please use the data of dummy users for all troubleshooting actions.

dig



Dig is a DNS lookup utility.

Example of arguments to use:

- Lookup for `www.example.com` on the DNS server with IP address `8.8.8.8`

```
@8.8.8.8 www.example.com
```

- Lookup for `repo-pub.awingu.com`. No DNS server is given, so the one configured in the Connectivity tab is used.

```
repo-pub.awingu.com
```

Dig returns the answer from the DNS server (see Answer Section in the output)

More information: [dig man page](#).

download-logs

Download the log files of the Awingu appliance. You can provide the following arguments to change the output format and time period:

- *From and To date:* By default, all logs from the last 7 days will be fetched. You can specify a from and a to date/time in UTC ISO format as arguments.
- *Json output:* By default, the different fields of a log statement are separated by spaces. By enabling newline-delimited Json output, the fields are available as Json properties and different log statements are separated by newlines.

A link to the log files will be shown in the output field. If the ZIP file is not ready yet, the file name starts with INPROGRESS. Every hour, ZIP files older than 1 hour will be cleaned up.

environment

These actions allow you to manage backups of the internal Awingu configuration.

The following actions are provided:

Action	Description
environment-backup-list	Generates a list of all available environment backups on the Awingu environment.
environment-backup-create	Creates a new backup of the Awingu environment.
environment-backup-restore	Restores the environment backups of the provided file. Not available when using an external database (only during the installation of a new appliance, e.g. when your Awingu node is corrupted or to move to a different hypervisor, ...).  Note that by default there are already periodic backups available.

More information on [Backup and recovery of the Awingu Environment](#).

ip-address-appliances

This action will display the IP configuration of each Awingu node in this cluster.

ldapsearch

Ldapsearch is an LDAP utility.

Example of arguments to use to simulate the default Awingu behavior when User1 signs in:

```
-LLL -H ldap://domain.example.com:389 -b 'dc=domain,dc=example,dc=com' -D 'DOMAIN\User1' -w 'password' '(&(sAMAccountName=User1)(objectClass=user))'
```

Argument definition:

- -LLL: show the output in LDIF format
- -H '<ldap\_url>': the URL of the LDAP server. Typically: 389 (no SSL). Mind that attempting to use LDAPS (port 636) will likely result in a failure, as a typical LDAP server uses a certificate that is not trusted by Awingu.
- -b '<base\_dn>': the starting point for the LDAP search
- -d '<level>': specify this argument with a value of 1 to see trace information.
- -D '<bind\_dn>': the distinguished name to bind to the LDAP directory. See Functions in User Connector tab:
  - function builtin.create\_domain\_bind\_name (default): '<domain\_name>\<username>'
  - function builtin.create\_username\_bind\_name: '<username>'
- -w '<password>': the password for the user to bind with
- -f '<filter>': LDAP search filter. The filter used by Awingu: '(&(sAMAccountName=<username>)(objectClass=user))'

Ldapsearch returns the LDAP search result. Interesting output lines are the ones starting with "memberOf", to see the list of AD security groups the user belongs to.

More information: [ldapsearch man page](#).

#### ping

Ping is a ICMP echo request sending tool.

Example of arguments to use:

- Ping 3 times to example.com:

```
-c 3 example.com
```

- Ping 5 times to example.com and only show IP addresses (n = numeric):

```
-c 5 -n example.com
```

More information: [ping man page](#).

#### shutdown-appliances

Performs a clean shutdown of all the appliances in this Awingu cluster.

#### sync-appliances-time

Initializes an immediate time synchronization against the configured NTP servers.

Afterwards, it's possible to confirm the time by running the **uptime** action.

#### tcpscan

Scans for open TCP ports. This action requires the following arguments:

- Host: hostname or IP address
- Port: single port, port range (e.g. 80-100) or comma-separated list of ports (e.g. 80, 443).

#### traceroute

Traceroute is a tool which prints the route packets trace to a network host

Example of arguments to use:

- Trace route to example.com

```
example.com
```

- Trace route to example.com and only show IP addresses (n = numeric):

```
-n example.com
```

More information: [traceroute man page](#).

#### udpscan

Scans for open UDP ports. This action requires the following arguments:

- Host: hostname or IP address
- Port: single port, port range (e.g. 80-100) or comma-separated list of ports (e.g. 80,443).

#### uptime

Uptime is a utility that tells how long the system has been running.

It shows some additional information, example:

```
15:21:06 up 2 days, 1:46, 0 users, load average: 0.19, 0.25, 0.25
```

- 15:21:06: current time of the Awingu VM in UTC. If the time is not correct, this can indicate a faulty NTP server.
- up 2 days, 1:46: number of days and hours since the last time the Awingu VM has booted up.
- 0 users: number of system users logged in to the system. Is typically 0.
- load average: system load of past 1, 5 and 15 minutes. The Awingu VM is overloaded if the value is higher than the number of CPUs.

More information: [uptime man page](#).

## Logging

In this section, the log level of the Application Gateway can be modified. This can be very helpful when troubleshooting an issue with applications. Changing the log level does not cause a service disruption.

Be aware however that if you change the log level to Info, Debug or Trace a lot more logs will be generated. As there is a maximum of 8 GB disk space allocated for logs, it will not have an impact on the overall appliance but logs of other services will get cleaned up sooner.

## System Settings - Configure

Domain specific settings are configured here:

- [Branding Configuration](#)
- [Feature Configuration](#)
- [User Connector Configuration](#)

## Branding Configuration



- [Multi-domain branding behavior](#)
- [Configuration options](#)
  - [General](#)
  - [Wide Logo](#)
  - [Square logo](#)
  - [Login Page](#)



The screenshot shows the 'Branding' configuration page in the Awingu system. The interface has a dark header with navigation links: 'DEV-AWINGU', 'Configure', 'Manage', 'Changes', and 'Global'. The main content area is titled 'Branding' and is divided into four sections: 'General', 'Wide Logo', 'Square Logo', and 'Login Page'. Each section contains configuration options with edit icons. The 'General' section includes 'Primary Color' (blue), 'Secondary Color' (blue), and 'Background Type' (Polygon). The 'Wide Logo' section includes 'Active Wide Logo' (Awingu) and 'Custom Wide Logo' (info icon). The 'Square Logo' section includes 'Active Square Logo' (Polygon) and 'Custom Square Logo' (a blue polygon logo). The 'Login Page' section includes 'Active Background' (Default (Polygon)), 'Custom Desktop Background' (info icon), 'Custom Tablet Background' (info icon), and 'Login Text' (displaying hostname, redeployed time, domain, and original login text).


DEV-AWINGU Configure Manage Changes Global

### Branding


#### General



Primary Color  

Secondary Color  


Background Type Polygon 



#### Wide Logo

Active Wide Logo Awingu 


Custom Wide Logo  



#### Square Logo



Active Square Logo Polygon 


Custom Square Logo  

#### Login Page

Active Background Default (Polygon) 

Custom Desktop Background  

Custom Tablet Background  

Login Text   
Hostname: nightly-external-ssl-4-0.c.awingu-dev.internal  
Redeployed: 2018-05-01 18:04 UTC  
Domain: DEV-AWINGU  
  
Original login text:  
Hostname: nightly-install-4-0  
Configured: 2018-05-01 17:48 UTC  
Domain: DEV-AWINGU

System Settings - © 2012-2018 Awingu N.V. - Eula 4.0

## Multi-domain branding behavior

Each domain has its own branding configuration:

- When you access the login page via the host header defined in [Domain Settings](#):
  - The branding of that domain is shown.
  - The *Domain* field on the login page is hidden.
- When you access the login page via a non-defined host header and there is only 1 domain configured:
  - The branding of that only domain is shown.
  - The *Domain* field on the login page is hidden.
- When you access the login page via a non-defined host header and there are multiple domains configured:

- The branding of the Default Domain is shown.
- The *Domain* field is shown on the login page.
- When you are logged in:
  - The branding of the applicable domain is shown.

## Configuration options

For each domain following settings can be shown:

### General

- **Primary Color:** The base color used to generate the background, polygon, pop-ups and favicon of the Awingu frontend for this domain. It is recommend to choose a bright color.
- **Secondary Color:** The color used in the Awingu frontend for buttons, folder icons, etc.
- **Background Type:** Whether to have the Awingu polygon background or a plain color. In both cases the primary color is used. Note that the background of the login page can be customized further on this page.

### Wide Logo

- **Active Wide Logo:** choose between the default Awingu logo and your own custom logo. The logo is shown on the top left of the Awingu frontend on the login page and the non-collapsed sidebar.
- **Custom Wide Logo:** upload an image for your custom logo:
  - Maximum file size: 100 KiB
  - Logo area: 159 x 70 px (when you scroll down, the logo area reduces to 159 x 30 px)

### Square logo

- **Active Square Logo:** choose between default Awingu polygon (with the color based on the primary color) and your own custom square logo. The logo is shown as favicon and on the collapsed sidebar.
- **Custom Square Logo:** PNG, JPG, SVG or ICO file of max. 2 MiB. Image needs to be square. Best results with PNG of 512 x 512 px or SVG image.

Note that if you have already accessed Awingu via the same browser before changing the square logo, you might need to clear your browser cache to see the favicon being changed.

### Login Page

- **Active Background:** choose between the default Awingu background image and your own custom background on the sign-in page.
- **Custom Desktop Background:** upload an image for your custom background for desktops (= screen width or height is more than 1280 pixels)
  - Maximum file size: 500 KiB
  - Recommended resolution: 3000x2100.
- **Custom Tablet Background:** upload an image for your custom background for tablets (= screen width or height is less than 1280 pixels)
  - Maximum file size: 150 KiB
  - Recommended resolution: 1280x860.
- **Login Text:** A free-field text, beneath the login credentials area, to put company specific information such as e.g. legal disclaimers. HTML tags are allowed.

Note about the background images:

- Rescaling (both scale-up and scale-down) is done while keeping the aspect ratio.
- When the scaled image is smaller than the canvas height, the upper and lower part will be cut-off equally.
- When the scaled image is smaller than the canvas width, the left and right part will be cut-off equally.
- The white banner with the logo will cover the upper part of the background image.

## Feature Configuration

- [Behavior](#)
- [Application session printing](#)
- [Application session sharing \(publicly\)](#)
- [File download](#)
- [Files](#)
- [File sharing \(publicly\)](#)
- [File upload](#)
- [Local clipboard](#)

### Features

Start typing to search

Name	User Restriction	Context Restriction
✓ Application session printing	Restricted	Restricted
✓ Application session sharing		
✓ Application session sharing publicly		
✓ File download		Restricted
✓ Files		
✓ File sharing		
✓ File sharing publicly		
✓ File upload		
✓ Local clipboard		

Items per page 10

⏪

⏩

1 / 1

⏪

⏩

### Feature Details

Name

File download

Description

Allows users to download files and folders on the Files page.

User Labels

all:

Context Policy Labels

country:BE,NL

### Behavior

All features listed are enabled for users depending on their User Labels and Context Policy Labels.

When the label of a user matches one the User Labels configured for a feature, the security context of the user will be validated against the Context Policy of that feature.

- To enable a feature for all users of the domain, please attach the predefined `all:` User Label to that feature and leave the Context Policy Labels field empty.
- To disable a feature for all users of the domain, please remove any User Labels from that feature.

To create custom labels and to find more information, please refer to [Label Management](#).

### Application session printing

When disabled, printing using the 'Virtual printer' within streamed application will not be possible. Printing using other printers configured on application servers will still be possible.

#### Application session sharing (publicly)

Defines if application session sharing is disabled all together or only disabled for public access. A list of possible scenarios:

The user does not belong to either *Application session sharing* and *Application session sharing publicly* user labels:

- The feature to share application sessions with other users is disabled.
- The Share session polygon button is not shown.

The user only belongs to *Application session sharing* users labels and his security context is valid:


- He can only share his application sessions with users from the same Awingu Domain.

The user belongs to *Application session sharing publicly* user labels and his security context is valid:

- He can share his application session with anyone as long as they have the share link.
- Note: it does not matter if he also belongs to the *Application session sharing* user labels.

The user belongs to *Application session sharing publicly* user labels and his security context is invalid:

- The button to enable session sharing will indicate that due to an invalid security context, session sharing is not allowed.



- Note: it does not matter if he also belongs to the *Application session sharing* user labels.

Note: This feature is accessible in a streamed app when clicking on the polygon and then on the share button.

#### File download

When disabled, the *Download* action is disabled for all files and folders on the Files page.

#### Files

When disabled, the *Folders* section on the Files page is removed. If File sharing is disabled, too, the complete Files page is removed.

#### File sharing (publicly)

Defines if file sharing is disabled all together or only disabled for public access. A list of possible scenarios:

The user does not belong to either *File sharing* and *File sharing publicly* user labels:

- The *Shares* section on the Files page is removed. If Files is disabled, too, the complete Files page is removed.
- The *Share* action is disabled for all files and folders.

The user only belongs to *File sharing* users labels and his security context is valid:

- He can only create file shares that can be accessed by someone from the same Awingu Domain.
- He will be able to choose Users where he can add specific users and groups or choose Domain so everyone from the Awingu Domain can access the file.

The user belongs to *File sharing publicly* user labels and his security context is valid:



- He can create files shares that can be accessed by anyone as long as they have the share link.
- Note: it does not matter if he also belongs to the *File sharing* user labels.

The user belongs to *File sharing publicly* user labels and his security context is invalid:

- The *Share* action will indicate that due to an invalid security context file sharing is not allowed.
- Note: it does not matter if he also belongs to the *File sharing* user labels.

#### File upload

When disabled, the *Upload* action is disabled for all files and folders on the Files page.

#### Local clipboard

When disabled, using you cannot copy/paste data from streamed applications to your local device and vice versa.

## User Connector Configuration


- Login Permissions
- Admin Permissions
- Account Settings Defaults
- Change Password Failed Message
- Multi-factor Authentication
- API Token Based Authentication
- Reverse Proxy
- Federated Authentication
- Automatic Logout
- Application Sessions
  - Application Recording
  - Session keep-alive
- External Audit Logging

## Login Permissions


Login Permissions

User Labels

all:



Context Policy Labels



In this section, you define which users are allowed to log in by using the label system.

- **User Labels:** Users with at least one of these labels will be able to log in (if all users can log in, add the "all:" label)
- **Context Policy Labels:** Users will only be able to log in if they have a valid context. The context can be configured using the MFA, network or country (2 char ISO 3166-1 alpha code) context policies labels. For network and country, you can define multiple options by using comma-separated values. When adding multiple policies, they must all be valid to be able to access the application. No labels means there are no restrictions.

See [Label Management](#) (User and Context Policy Labels) for more information and examples.

### Enable Multi-Factor Authentication on Login

To enable Multi-Factor Authentication for all users when logging in, the 'mfa:required' context label will need to be added to the Context Policy Labels.

## Admin Permissions

Admin Permissions		
User Labels	group:Awingu Admins ÇαBøÿ #*!@&!%*[]	
Context Policy Labels	country:BE,NL	

In this section, you define which users are Domain Administrators and which security context is required to be a Domain Administrator.

- **User Labels:** Users with at least one of these labels will be Domain Administrators
- **Context Policy Labels:** Users will only receive the Domain Administrator role if their context is valid. The context can be configured using the MFA, network or country (2 char ISO 3166-1 alpha code) context policies labels. For network and country, you can define multiple options by using comma-separated values. When adding multiple policies, they must all be valid to be able to access the feature.

See [Label Management](#) (User and Context Policy Labels) for more information and examples.

## Account Settings Defaults

## Account Settings Defaults

**Keyboard layout** United States - English



**Language** English



**Guided tours** Enabled



**Polygon** Visible



This section allows you to define default profile values for users of a domain.

- **Keyboard layout:** the default configured keyboard layout for users of this domain
- **Language:** the Awingu interface's language for users of this domain. By default Awingu will use the browser's default language, if this is unknown to Awingu, it will fall back to this language configured for the domain.
- **Guided tours:** defines if the guided tours are shown for new users of this domain. Note: guided tours will not appear when the browser size is too small.
- **Polygon:** defines if the polygon is shown by default for new users of this domain.

Please note that a user can always update these settings on his/her Account Settings page.

## Change Password Failed Message

### Change Password Failed Message

**State** Enabled



**Message** Passwords need to start with an \*

When users try to change their password but fail due to not meeting the minimum complexity requirements, a custom error message can be added by the administrator.

This message can be used to inform the users about specific requirements.

The screenshot shows a 'Change password' form with three input fields. The first field contains '\*\*\*\*\*', the second contains '\*\*', and the third contains '\*-'. Below the fields, a red error message reads: 'Could not change password for user jonasvdt: Your new password likely does not meet the minimum complexity requirements or you are trying to change it too soon.' Below this, a smaller red message says 'Passwords need to start with an \*'. At the bottom is a blue 'Change password' button.

## Multi-factor Authentication

DEV-AWINGU
Configure
Manage
Global

### Multi-factor Authentication

Mode
RADIUS

Servers
radius.awingu.com

Port
1812

Secret
\*\*\*\*\*

LDAP Username Attribute
sAMAccountName

Cancel
Apply

Whitelisted Subnets
172.22.2.0/24

Cancel
Apply

Trusted Browser
☐ Enabled
☒ Disabled

When this setting is enabled, users will be allowed to mark their browser as being "trusted" and skip multi-factor authentication for 30 days.

Cancel
Apply

System Management Console - © 2012-2017 Awingu N.V. - Eula
3.6.1

Awingu provides out-of-the-box one-time-password (OTP) support and integrates with several Multi-factor Authentication providers.

When enabled, each time a user wants to sign in to Awingu, not only do the LDAP/AD credentials need to be provided, but (s)he will need to generate a token via an authenticator app or a hardware token.

Multi-factor authentication is disabled by default but can be enabled by selecting the desired integration mode.


**i** When using a **built-in Workspace OTP** method, we highly recommend "time-based" in most cases since it's more secure and easier to sync on multiple devices.  
For more details on the user experience of these built-in methods, see [Using Awingu built-in OTP](#)

- **Workspace OTP: Counter Based:** Leverages the built-in counter-based one-time-password (OTP) functionality
  - **Issuer name:** The company name shown to the user in the OTP application.
  - **Manage User Token Count:** Allows resetting the token count for specific users. When the token is reset, the user will need to set up his/her device again.
- **Workspace OTP: Time Based:** Leverages the built-in time-based one-time-password (OTP) functionality
  - **Issuer name:** The company name shown to the user in the OTP application.
  - **Manage User Token Count:** Allows resetting the token count for specific users. When the token is reset, the user will need to set up his/her device again.
- **Duo Security:**  
For more information: [Integrating Awingu with DUO](#)
  - **API Hostname:** The Duo Auth API configured hostname
  - **Integration Key:** The Duo Auth API integration key
  - **Secret Key:** The Duo Auth API secret key


- **RADIUS:** The token will be validated using an external RADIUS server (Note: Chap (v2) authentication schema not supported) The RADIUS server needs to be configured to not increase the counter for a failed attempt. For FreeRadius, this means adding `no_increment_hotp` to auth requisite in the `radiusd` config file.
  - **Servers:** Comma-separated list of hosts or IP addresses of the RADIUS server
  - **Port:** The Port number the RADIUS server is listening on
  - **Secret:** The secret configured in the RADIUS server

For all MFA providers, you can configure the following additional settings:


- **LDAP Username Attribute:** the LDAP attribute used to provide a username to the provider, via the **LDAP Username Attribute** field. One of the following attributes can be chosen:
  - **sAMAccountName:** Corresponds with the login name without UPN on Windows Domain Controller.
  - **NETBIOSsAMAccountName:** Same as sAMAccountname, but with the NetBIOS name prefixed.
  - **userPrincipalName:** Corresponds with the UPN on Windows Domain Controller.
  - **uid:** Corresponds with the login name without UPN on OpenLDAP. This should not be selected when initially authenticating against a Windows Active Directory.
- **Whitelisted subnets:** Comma-separated list IPv4 subnets. For users accessing Awingu from these subnets, Multi-factor Authentication will be skipped.

 When using a reverse proxy server in front of Awingu, please make sure you forward the client's originating IP address using the *X-Forwarded-For* header. See [SSL offloader, reverse proxy or loadbalancer settings](#).

- **Whitelisted User Labels:** For users that belong to one of the user labels Multi-factor Authentication will be skipped.
- **Trusted Browser:** If enabled, users will be asked if they trust the device. If so, no MFA will be required for 30 days. Note that if the user deletes her browser cookies, MFA will be required again.

 The management user (created during installation) does not need to use any form of MFA to log in. To avoid access with that user from the public internet, you can limit subnets from where that user can log in on [General Information](#).

## API Token Based Authentication



Next to basic authentication with username and password, administrators can use authentication with an API token. This is useful for the automation of Awingu through scripts using the REST API. As this token never expires, it is recommended to limit the usage of the token to the network of the computers/servers where the scripts are running using Whitelisted Subnets.

Note: if Whitelisted Subnets are disabled for API Token Based Authentication, the API token can be used from anywhere.

Administrators can generate an API token from their **Account settings** page under **Manage API token**:

**Awingu.com** Manage API token Close x

When automating the configuration by means of a REST API, it is possible to use a token to bypass logging in and the multi-factor authentication: you will not be prompted to fill in a username and password.

Only administrators can generate a token for their username. When generating a new token, the previous token is disabled.

Please refer to the Administration Manual for more information about REST API-based configuration.

**Warning:** A token is equivalent to a password and should therefore be kept secret. Anyone with a token has the same access rights and configuration permissions as the user who generated it.

Please enter your password to generate or disable a token:

Password

Generated token for dev-awingu\kerwyny:

Generate new token

Disable token

Licensed to Awingu  
Awingu 4.1 © 2012 - 2018

See [Automate Awingu via the REST API](#) for a PowerShell example.

## Reverse Proxy

DEV-AWINGU Configure Manage Changes Global

### Reverse Proxy

Default Login Host Header: dev-awingu.com

The host header which the user will be redirected to if he is logged out when trying to access a proxied web application in this domain.

Cancel Apply

System Settings - © 2012-2018 Awingu N.V. - Eula 4.1

Here you set the default host header for this domain that will be used when accessing a reverse-proxied web application.

## Federated Authentication

**i** See [Awingu Single Sign On \(SSO\)](#) for detailed instructions on how to set up Single Sign-On and SAML/OpenID connect Authentication.

Next to the standard username/password login, Awingu is also able to do a full Single Sign-on (SSO) via an external Identity Provider.

When switching to SSO the login becomes a 2-step process.

Firstly Awingu no longer does the authentication of the user itself, but this is handled by an external Identity Provider (IDP). As the external IDP doesn't expose the passwords and the Microsoft Remote Desktop Protocol (RDP) doesn't support ticket/token-based logins, in a second step, the credential-based login towards back-end systems (remote app, VDI, storage, ...) is replaced by a certificate-based login mechanism.



Enabling the Federated Authentication can be done in 2 steps/levels:

1. When enabling Pre-Authentication, the user will need to authenticate with the configured identity provider before authenticating in Awingu. This adds an additional validation step but will still require that the user provides his Windows password to the Awingu Appliance. See [Enabling Pre-Authentication \(PreAuth\)](#) for integration instructions.
2. Once Pre-Authentication is working, the password step can be replaced by a full Single Sign-On process based on the certificate/Kerberos login mechanism. See [Enable Single Sign-On \(SSO\)](#) for integration instructions.

## Automatic Logout

Changes to any of these settings will only be applied when the user signs in to the Awingu workspace again. It does not affect logged-on users.

**Automatic Logout:** Enable or disable this feature.

**Inactivity timeout:** When automatic logout is enabled, a specific timeout can be configured in seconds. The default is 3600 seconds (1 hour). User sessions may remain open for up to 1 minute after the timeout has been reached. The minimum is 2 minutes, the maximum is 4 hours.

**User Labels:** Define the users for whom the automatic logout is enabled. The built-in management user however will always automatically be logged out after 10-15 minutes.

The default

## Application Sessions

Application Sessions

Recordings Upload	Disabled	
Recordings Upload URL		
Recorded Users	group:Recorded Users Canley #712&W11	
Keepalive Disconnected Timeout	15	

This section applies to streamed applications (RDP apps and RemoteApps).

### Application Recording

Awingu allows saving recordings of streamed application sessions. When a session recording ends, the resulting recording file is automatically transferred from the Awingu appliance's local disk to a back-end server you can define. Those recording files can be played with the **Recorded Session Player**, which is accessible to all users in a group with the *admin* label.

When this feature is enabled, the following streamed app sessions will be recorded:

- All applications with the *record* label (cf. [Application Management](#))
- All applications started by users specified using labels in the **Recorded Users** setting.

Settings:

- **Recordings Upload:** Enable or disable the uploading of recorded sessions of streamed applications to the specified upload URL.
- **Recordings Upload URL:** Specifies destination for recorded sessions in the following specific structure:
  - For HTTP: <http://username:password@server:port/path/to/save>
  - For SMB/CIFS: <smb://DOMAIN\username:password@server:port/path/to/save>Note that DOMAIN should match an **Awingu domain name**, which might be different from the NetBIOS name or Windows FQDN domain name, and must be upper case.



- For privacy reasons, please make sure that only authorized personnel can access the server defined in the Recordings Upload URL.
- Known limitation: certain special characters in the password are not allowed. This includes a space and these characters: # / :
- When uploading fails, recorded sessions are kept internally for up to 7 days on the Awingu node. If uploading starts working again, those recorded sessions will still be uploaded.

Session keep-alive

**Keepalive Disconnected Timeout:** Number of minutes the streamed application session will be kept alive. A session can be kept alive when the end users accidentally close their browser or browser tab, when they lose network connectivity, or when they log out without closing their applications. After the time-out, the application will be terminated (unsaved changes will be lost). The maximum value is 1440 minutes (1 day).

## External Audit Logging

Awingu allows you to forward all audit logs to an external system using the HTTP protocol.

This can be used to integrate Awingu with external systems such as security tools (e.g. SIEM tools), reporting tools or automation systems.



This functionality can only be used when the audit logs are migrated to the DB on Awingu 5.0

To enable audit log forwarding, only a URL is required, optionally you can provide credentials for Basic Authentication.

### External Audit Logging

State

☒ Enabled  
☐ Disabled

External Audit System Url

Url of external audit system, internal audit logs are sent to this endpoint  
Required

Basic Authentication

☒ Enabled  
☐ Disabled

When enabled an authorization header will be added to requests made to the External Audit System Url.

Username

Username used when Basic Authentication is enabled for external audit  
Required

Password

Password used when Basic Authentication is enabled for external audit  
Required

- **State:** Enable or disable the forwarding of audit logs for this domain
- **External Audit System URL:** The URL to which all audit logs will be forwarded.
- **Basic Authentication:** Enable to add an authorization header to all requests with the specified credentials



- **Username:** (Optional) Username to use for Basic Authentication
- **Password:** (Optional) Password to use for Basic Authentication

More information on how you can integrate *External Audit Logging* can be found on [External Audit Logging](#)

## System Settings - Manage

Domain specific objects can be managed here:

- [Application Management](#)
- [Application Server Management](#)
- [Category Management](#)
- [Drive Management](#)
- [File Type Management](#)
- [Label Management](#)
- [User Management](#)


## Application Management

- [Introduction](#)
- [Adding applications manually](#)
  - [General Settings](#)
  - [Desktop Application](#)
  - [RDP Application](#)
  - [Remote Applications](#)
  - [Reverse Proxied Web Application](#)
  - [Web Application](#)
- [Importing applications with a CSV file](#)
  - [Generating a CSV file](#)
  - [Importing a CSV file](#)
- [Configuring shortcut buttons](#)

## Introduction

This page allows managing applications for each domain. Awingu supports the following types of applications:

- Streamed Applications, using the Remote Desktop Protocol. Awingu supports 3 flavors:
  - **RDP Application**: will make use of the regular Remote Desktop Protocol.
  - **Desktop Application**: similar to the RDP Application type except that the Command, Working Folder and File Types properties do not have to be provided.
  - **Remote Application**: an extension to the Remote Desktop Protocol. RemoteApp needs to be supported by your application server, and your applications need to be exposed over RemoteApp. It has several advantages over regular RDP applications:
    - The window selector (Windows button at the top of the app) is available.
    - The experience on tablets is smoother (especially when rotating the tablet and zooming in/out).
    - The app sharing experience is better.
    - It uses fewer resources on the application server.

 When both RemoteApp and RDP Applications are supported on your application server, we strongly recommend using RemoteApp.

- Web Applications. Web applications are not served through the RDP gateway. Instead, when launching a web application, a separate browser tab will be opened. You can specify whether to use the **built-in reverse proxy** for HTTP(S).
  - **Web Application**: The browser will be redirected directly to the URL of the web application, which needs to be reachable from the end-user's device.
  - **Reverse Proxied Web Application**:
    - The browser will be redirected to a configured source hostname (e.g. intranet.mycompany.com), which resolves (through DNS) to the same IP as the Awingu environment.
    - Awingu will check if the user is authenticated and has the right to access the application. If so, the content of the web application is reverse proxied through Awingu.
    - Awingu can be configured to rewrite HTTP headers (including cookies) and the body to replace all occurrences of the destination URL with the source hostname.
    - If Awingu is configured to do SSL offloading, it also behaves as an SSL offloader for an HTTP web application.
    - If the web application supports Basic Authentication, the username and password given to Awingu can be provided to the web application (= Single Sign-On, SSO).

There are however some limitations:

- When the rewrite option is enabled, the web application might still have links to the original destination URL instead of the configured source hostname. This might be because it uses content that is not text/html or because the URL is obfuscated or encoded. Therefore, if the web application has support to run behind a reverse proxy, we recommend not using the rewrite option in that case.
- The reverse proxy uses a connection pool toward the web application. This means NTLM authentication cannot work because it needs a persistent connection to the browser.
- Uploading a file to a reverse proxied web application is limited to 100 MB.

Other references:

- To define the application servers, please refer to [Application Server Management](#).
- To prepare the application servers, please refer to [Integrating with existing Windows environment](#).
- Awingu does NOT manage the actual applications on the application server(s). There are commercial products available to do so.

## Adding applications manually

Click on **Add** and choose the type of application you would like to add.

Items per page 10 ▼

Add ▼ Import from File

- Desktop Application
- RDP Application
- Remote Application
- Reverse Proxied Web Application
- Web Application

#### General Settings

The following general settings apply to all types of applications:

- **Name:** The application name as it will appear in the Awingu user interface.
- **Description:** Description of the application, not visible to end-users.
- **Icon:** The application icon that will be visible to the end-user in the Awingu user interface. When you upload an icon, it is saved to the database and automatically propagated to all Awingu front-end instances in your Awingu deployment. Only ICO, JPG and PNG are allowed.
- **Categories:** Associate zero, one or more application [categories](#) to this application.
- **User Labels:** User labels are used in the process of authorizing users to applications. Only users with labels assigned in this field will see the application in the Applications tab (use *all:* to be visible to all users). See chapter on [Label Management](#) for more information.
- **Show in Applications:** When disabled, the application will not be shown on the Applications page in Awingu. Note: This only hides the application. If the user has the appropriate permissions for the application, he will still be able to access the application via the Direct link.
- **Labels:** Add labels to applications to group them. These groups can be used to filter application servers in lists and reports. This is also used to enable specific features:
  - The *smartcard:* label is used to enable smart card access for this application (see [Smart Card Redirection](#) for more information).
  - The *record:* label is used to activate [session recording](#) for this application for all users (needs to be enabled).
  - The *rewritegroup:xxxxx* label is useful when multiple web applications are reverse proxied by Awingu and are linking to each other. By default, Awingu will only rewrite URLs per reverse proxy web application. Note: make sure to first create this label in Manage > Labels.
- **Auto Start Labels:** Start the application automatically at login for users with defined matching labels. The set of labels you can define are the same as *User Labels*. Use "all:" to enable the auto start of the application for all users. The application will be started in the background and will be available to the user via the sidebar. Note: recorded applications will not be started automatically and this feature is not compatible with the option Ask for Credentials.

#### Desktop Application

Add Desktop Application

Name

Required

Description

Icon

No file chosen

Image file (max 100 KiB)

Categories

This application will be shown in the selected categories.

User Labels

The application will only be visible for users with a matching user label. Use "all:" to assign the application to all users; keep empty to have no users assigned.

Context Policy Labels

Restrict this application to only be accessible within the provided security context. The context can be configured using the mfa, network or country (2 char ISO 3166-1 alpha code) context policies labels. For network and country, you can define multiple options by using comma separated values. When adding multiple policies, they must all be valid to be able to access the application.

Server Labels

The Remote/RDP application will be launched on application servers with a matching server label. Note that each application server has a server label named "appserver:<server name>".

- **Server Labels:** Server labels identify on which application servers this application is available. When a user launches this application, these labels will be used to generate a candidate list of application servers to connect to.
- **Context Policy Labels:** Restrict this application to only be accessible within the provided security context. The context can be configured using the mfa, network or country (2 char ISO 3166-1 alpha code) context policies labels. For network and country, you can define multiple options by using comma-separated values. When adding multiple policies, they must all be valid to be able to access the application. See the Label Management page for more information and examples.

**Show in Applications** ☒ Enabled  
☐ Disabled

**Labels**   
 Enter labels to logically group applications together or to enable certain features (smartcard, record). You can use these labels in the search field and in the Dashboard.

**Auto Start Labels**   
 The application will start automatically at login for users with a matching user label. Use "all" to enable auto start for all users. Recorded applications will not be started automatically.

**Unicode Keyboard Support** ☒ Enabled  
☐ Disabled

**Color Depth**

**Start in Foreground** ☐ Enabled  
☒ Disabled  
 If this application starts automatically (see "Auto Start Labels"), this application will start in the foreground (max. 1 per domain).

**Concurrent Usage** ☐ Enabled  
☒ Disabled  
 Allow a user to open multiple instances of this application at the same time.

**Ask for Credentials** ☐ Enabled  
☒ Disabled  
 Can only be enabled when there are no auto start labels assigned.  
 A user will have to provide credentials to login to the application.

**Notifications** ☒ Enabled  
☐ Disabled  
 Allow this application to send notifications to a user which will be shown in the sidebar.

**Minimum Size** ☐ Enabled  
☒ Disabled  
 When enabled, the minimum size is applied to all Awingu displays in the application session hosting this application. The application can be panned when the browser window is smaller than the Awingu display.  
 Can be used together with maximum size to configure a fixed size for this application.

**Maximum Size** ☐ Enabled  
☒ Disabled  
 When enabled, the maximum size is applied to all Awingu displays in the application session hosting this application. The application is positioned top left when the browser window is bigger than the Awingu display.  
 Can be used together with minimum size to configure a fixed size for this application.

Cancel Add

- **Unicode Keyboard Support:** Disable when the application (e.g. software made with Qt) does not support the Unicode Keyboard that Awingu uses in the RDP Gateway. We suggest first trying with Unicode Keyboard Support enabled: when typing in the application results in a repetition of the first typed character (or other odd behavior), then you should disable the Unicode support. The advantage of Unicode Keyboard is better recognition of special characters on keyboards and the use of on-screen keyboards on tablets.
- **Color Depth:** Defines how many bits per pixel should be used. The higher the color depth, the higher the detail of the application but it will also take more processing and bandwidth. Default is set at 16bpp and can be increased to 24bpp or 32bpp.
- **Start in Foreground:** If enabled and the application auto starts at login, it will immediately be presented to the user and the workspace will be skipped.
- **Concurrent Usage:** Allow a user to open multiple instances of this application at the same time. This is enabled by default. A common use case to disable this option is for an application that accesses a predefined user-owned file, like Microsoft Outlook (only one process can access the user's mailbox).
- **Ask for Credentials:** A user will have to provide credentials to log in to the application (otherwise Awingu provides the login credentials to the application server). This is useful when the Server Labels are linked to application servers that are not joined to the Windows domain. Can only be enabled when there are no Auto Start Labels assigned.
- **Notifications:** Allow this application to send notifications to a user (default enabled). Those notifications will be shown in the sidebar as a red dot. If the application provides a relevant hover text for the systray icon, this will also be shown to the user.
- **Minimum Size:** When enabled, you can set the minimum size to be able to use this application on devices with small screens. If the visible part of the application session is smaller than this minimum size, you will be able to pan inside the session.
- **Maximum Size:** When enabled, you can set the maximum size of the application. When the browser window is bigger than the application, the application will be positioned in the top left. Can be used together with the minimum size feature to configure a fixed size for this application.

RDP Application

Add RDP Application

**Name**   
Required

**Description**

**Icon**  No file chosen  
Image file (max 100 KB)

**Categories**   
This application will be shown in the selected categories.

**Command**   
The full path to the program executable (e.g. c:\windows\calc.exe).  
Required

**Working Folder**

**User Labels**   
The application will only be visible for users with a matching user label. Use "all" to assign the application to all users; keep empty to have no users assigned.

**Context Policy Labels**   
Restrict this application to only be accessible within the provided security context. The context can be configured using the mfa, network or country (2 char ISO 3166-1 alpha code) context policies labels. For network and country, you can define multiple options by using comma separated values. When adding multiple policies, they must all be valid to be able to access the application.

**Server Labels**   
The RemoteRDP application will be launched on application servers with a matching server label. Note that each application server has a server label named "appserver.<server name>".

**File Types**

Available items		Chosen items
acgi	>	
ai	<	
asc		
avi		
bas		
bat		
bif		
c		
com		
conf		
css		

Select all Select all

Advanced Settings ▾


Cancel Add

- **Command:** The full path to the program executable. Mind that parameters are not allowed here.
- **Working Folder:** Folder into which an application needs to be launched, i.e. the current working directory. This can remain empty.
- **Context Policy Labels:** Restrict this application to only be accessible within the provided security context. The context can be configured using the mfa, network or country (2 char ISO 3166-1 alpha code) context policies labels. For network and country, you can define multiple options by using comma-separated values. When adding multiple policies, they must all be valid to be able to access the application. See the Label Management page for more information and examples.
- **Server Labels:** Server labels identify on which application servers this application is available. When a user launches this application, these labels will be used to define a list of applicable servers to connect to.
- **File Types:** Associate zero, one or multiple file types with this application for viewing or editing.

**i** If you want to associate file types with applications, such that you can open files with a linked application when clicking on the file, you need to make a few additional configuration steps:

On your application server, make sure you have enabled the option "**Allow any command-line arguments**" for your RemoteApp.

If you want certain files (from Awingu's Files tab) to be opened with this RemoteApp, mind that you will need to **specify the UNC path** for any drives you publish. See [Drive Management](#) for more details.





**Show in Applications** ☒ Enabled  
☐ Disabled

**Labels**   
Enter labels to logically group applications together or to enable certain features (smartcard, record). You can use these labels in the search field and in the Dashboard.

**Auto Start Labels**   
The application will start automatically at login for users with a matching user label. Use "all" to enable auto start for all users. Recorded applications will not be started automatically.

**Unicode Keyboard Support** ☒ Enabled  
☐ Disabled

**Color Depth**

**Start in Foreground** ☐ Enabled  
☒ Disabled  
If this application starts automatically (see "Auto Start Labels"), this application will start in the foreground (max. 1 per domain).

**Concurrent Usage** ☒ Enabled  
☐ Disabled  
Allow a user to open multiple instances of this application at the same time.

**Ask for Credentials** ☐ Enabled  
☒ Disabled  
Can only be enabled when there are no auto start labels assigned.  
A user will have to provide credentials to login to the application.

**Notifications** ☒ Enabled  
☐ Disabled  
Allow this application to send notifications to a user which will be shown in the sidebar.

**Minimum Size** ☐ Enabled  
☒ Disabled  
When enabled, the minimum size is applied to all Awingu displays in the application session hosting this application. The application can be panned when the browser window is smaller than the Awingu display.  
Can be used together with maximum size to configure a fixed size for this application.

**Maximum Size** ☐ Enabled  
☒ Disabled  
When enabled, the maximum size is applied to all Awingu displays in the application session hosting this application. The application is positioned top left when the browser window is bigger than the Awingu display.  
Can be used together with minimum size to configure a fixed size for this application.

- **Unicode Keyboard Support:** Disable when the application (e.g. software made with Qt) does not support the Unicode Keyboard Awingu uses in the RDP Gateway. We suggest first to try with Unicode Keyboard Support enabled: when typing in the application results in a repetition of the first typed character (or other odd behavior), then you should disable the Unicode support. The advantage of Unicode Keyboard is better recognition of special characters on keyboards and the use of on-screen keyboards on tablets.
- **Color Depth:** Defines how many bits per pixel should be used. The higher the color depth, the higher the detail of the application but it will also take more processing and bandwidth. Default set at 16bpp and can be increased to 24bpp or 32bpp.
- **Start in Foreground:** If enabled and the application auto starts at login, it will immediately be presented to the user and the workspace will be skipped.
- **Concurrent Usage:** Allow a user to open multiple instances of this application at the same time. This is enabled by default. A common use case to disable this option is for an application that accesses a predefined user-owned file, like Microsoft Outlook (only one process can access the user's mailbox).
- **Ask for Credentials:** A user will have to provide credentials to log in to the application (otherwise Awingu provides the login credentials to the application server). This is useful when the Server Labels are linked to application servers that are not joined to the Windows domain. Can only be enabled when there are no Auto Start Labels assigned.
- **Notifications:** Allow this application to send notifications to a user (default enabled). Those notifications will be shown in the sidebar as a red dot. If the application provides a relevant hover text for the systray icon, this will also be shown to the user.
- **Minimum Size:** When enabled, you can set the minimum size to be able to use this application on devices with small screens. If the visible part of the application session is smaller than this minimum size, you will be able to pan inside the session.
- **Maximum Size:** When enabled, you can set the maximum size of the application. When the browser window is bigger than the application, the application will be positioned in the top left. Can be used together with the minimum size feature to configure a fixed size for this application.

Remote Applications

Add Remote Application

Name
Required

Description

Icon
 No file chosen  
Image file (max 100 KB)

Categories
This application will be shown in the selected categories.

Alias
Enter the remote application alias (e.g. winword)  
Required

User Labels
The application will only be visible for users with a matching user label. Use "all" to assign the application to all users; keep empty to have no users assigned.

Context Policy Labels
Restrict this application to only be accessible within the provided security context. The context can be configured using the mfa, network or country (2 char ISO 3166-1 alpha code) context policies labels. For network and country, you can define multiple options by using comma separated values. When adding multiple policies, they must all be valid to be able to access the application.

Server Labels
The Remote/RDP application will be launched on application servers with a matching server label. Note that each application server has a server label named "appserver:<server name>".

File Types

Available items

Chosen items

- **Alias:** Provide the Remote Application alias.
- **Context Policy Labels:** Restrict this application to only be accessible within the provided security context. The context can be configured using the mfa, network or country (2 char ISO 3166-1 alpha code) context policies labels. For network and country, you can define multiple options by using comma-separated values. When adding multiple policies, they must all be valid to be able to access the application. See the Label Management page for more information and examples.
- **Server Labels:** Server labels identify on which application servers this application is available. When a user launches this application, these labels will be used to define a list of applicable servers to connect to.
- **File Types:** Associate zero, one or multiple file types with this application for viewing or editing. See the RDP File Types property above for additional information.

**Show in Applications** ☒ Enabled  
☐ Disabled

**Labels**   
Enter labels to logically group applications together or to enable certain features (smartcard, record). You can use these labels in the search field and in the Dashboard.

**Auto Start Labels**   
The application will start automatically at login for users with a matching user label. Use "all" to enable auto start for all users. Recorded applications will not be started automatically.

**Unicode Keyboard Support** ☒ Enabled  
☐ Disabled

**Color Depth**

**Start in Foreground** ☐ Enabled  
☒ Disabled  
If this application starts automatically (see "Auto Start Labels"), this application will start in the foreground (max. 1 per domain).

**Concurrent Usage** ☒ Enabled  
☐ Disabled  
Allow a user to open multiple instances of this application at the same time.

**Ask for Credentials** ☐ Enabled  
☒ Disabled  
Can only be enabled when there are no auto start labels assigned.  
A user will have to provide credentials to login to the application.

**Notifications** ☒ Enabled  
☐ Disabled  
Allow this application to send notifications to a user which will be shown in the sidebar.

**Session Merge** ☐ Enabled  
☒ Disabled  
When enabled, the application can be merged into an existing RDP session. This only happens when the new application shares a number of settings with the existing applications in the session.  
Shared application settings:  

- Allow Session Merge enabled
- Protocol is Remote Application
- Same Application Server
- Equal Recording settings
- Equal Smartcard settings
- Equal Unicode Keyboard Support settings
- Ask for Credentials disabled
- Same Context Policy Labels

RDP sessions instantiated by an automatically started application will block application merging for 10 seconds.

**Minimum Size** ☐ Enabled  
☒ Disabled  
When enabled, the minimum size is applied to all Awingu displays in the application session hosting this application. The application can be panned when the browser window is smaller than the Awingu display.  
Can be used together with maximum size to configure a fixed size for this application.

**Maximum Size** ☐ Enabled  
☒ Disabled  
When enabled, the maximum size is applied to all Awingu displays in the application session hosting this application. The application is positioned top left when the browser window is bigger than the Awingu display.  
Can be used together with minimum size to configure a fixed size for this application.

- **Unicode Keyboard Support:** Disable when the application (e.g. software made with Qt) does not support the Unicode Keyboard Awingu uses in the RDP Gateway. We suggest first trying with Unicode Keyboard Support enabled: when typing in the application results in a repetition of the first typed character (or other odd behavior), then you should disable the Unicode support. The advantage of Unicode Keyboard is better recognition of special characters on keyboards and the use of on-screen keyboards on tablets.
- **Color Depth:** Defines how many bits per pixel should be used. The higher the color depth, the higher the detail of the application but it will also take more processing and bandwidth. The default is set at 16bpp and can be increased to 24bpp or 32bpp.
- **Start in Foreground:** If enabled and the application auto starts at login, it will immediately be presented to the user and the workspace will be skipped.
- **Concurrent Usage:** Allow a user to open multiple instances of this application at the same time. This is enabled by default. A common use case to disable this option is for an application that accesses a predefined user-owned file, like Microsoft Outlook (only one process can access the user's mailbox).

- **Ask for Credentials:** A user will have to provide credentials to log in to the application (otherwise Awingu provides the login credentials to the application server). This is useful when the Server Labels are linked to application servers that are not joined to the Windows domain. Can only be enabled when there are no Auto Start Labels assigned.
- **Notifications:** Allow this application to send notifications to a user (default enabled). Those notifications will be shown in the sidebar as a red dot. If the application provides a relevant hover text for the systray icon, this will also be shown to the user.
- **Session Merge:** When enabled, the application can be merged into an existing application session. The merge will only happen when the new application shares a number of settings with the existing applications in the session.
  - Required shared application settings:
    - Allow Session Merge enabled
    - Protocol is Remote Application
    - Same Application Server
    - Equal Recording settings
    - Equal Smartcard settings
    - Equal Unicode Keyboard Support settings
    - Ask for Credentials disabled
    - Same Context Policy labels
    - Same RDS Collection labels
  - The existing application session to the same application server must still be active (not disconnected).
  - Advantages: Applications will start faster and consume fewer resources on the application server.
  - Side effects:
    - Users will see multiple applications in the same application session when they resize or minimize one of the applications.
    - Applications that are merged will also be shown together in the list of Active Sessions in the sidebar of the user.
    - The color depth setting of the merged application will be ignored.
- **Minimum Size:** When enabled, you can set the minimum size to be able to use this application on devices with small screens. If the visible part of the application session is smaller than this minimum size, you will be able to pan inside the session.
- **Maximum Size:** When enabled, you can set the maximum size of the application. When the browser window is bigger than the application, the application will be positioned in the top left. Can be used together with the minimum size feature to configure a fixed size for this application.

Reverse Proxied Web Application

Add Reverse Proxied Web Application

Name

Required

Description

/

Icon

Browse... No file selected.

Image file (max 100 KiB)

Categories

This application will be shown in the selected categories.

Destination URL

Provide the internal URL of the website, which must be accessible to Awingu. If your destination URL also contains a path (e.g. https://internal-app.somedomain.org/somepath) and you try to access the application directly instead of through the Awingu workspace, you'd still need to specify the path as well, not just the DNS name from the source headers.

Required

Source Host Header

This is the hostname (DNS name) shown to the user when opening this web application in their browser (e.g. intranet-pub.mycompany.com). The host header should resolve to the Workspace, but should be different than the one(s) used to access the workspace. E.g. if your Workspace is reachable via workspace.company.com make sure you have a second DNS record (intranet-pub.mycompany.com) pointing to your Workspace and use that DNS name as source host header.

Required

User Labels

The application will only be visible for users with a matching user label. Use "all" to assign the application to all users; keep empty to have no users assigned.

Context Policy Labels

Restrict this application to only be accessible within the provided security context. The context can be configured using the mfa, network or country (2 char ISO 3166-1 alpha code) context policies labels. For network and country, you can define multiple options by using comma separated values. When adding multiple policies, they must all be valid to be able to access the application.

Advanced Settings

Show in Applications

☒ Enabled

☐ Disabled

Labels

Enter labels to logically group applications together or to enable certain features (smartcard, record). You can use these labels in the search field and in the Dashboard.

Auto Start Labels

The application will start automatically at login for users with a matching user label. Use "all" to enable auto start for all users. Recorded applications will not be started automatically.

Destination Host Header

☒ Default

☐ Custom

This is the host header passed to the server hosting the web application.

- Default: uses the host name extracted from the Destination URL. This is the case if the server hosting the web application is not aware that it is reachable through a reverse proxy.
- Custom: typical use case is to enter the same value of the Source Host Header, which means that the server hosting the web application is aware of the presence of a reverse proxy (which might be a configuration option of the web application).

Rewrite Content

☒ Enabled

☐ Disabled

Rewrite all URLs in the returned content (HTTP headers, cookies and text/html body) from the web application by replacing the host of the Destination URL with the specified Source Host Header. Rewriting is typically needed when the server hosting the web application is not aware that it is reachable through a reverse proxy.

Single Sign-On

☐ Enabled

☒ Disabled

Cancel

Add

- Destination URL:**  
 Provide the internal URL of the website, which must be accessible to Awingu.  
 If your destination URL also contains a path (e.g. https://internal-app.somedomain.org/somepath ) and you try to access the application directly instead of through the Awingu workspace, you'd still need to specify the path as well, not just the DNS name from the source headers.
- Source Host Header:** When a user opens this web application, the Source Host Header will be shown in the URL bar of their browser. This host header should resolve via DNS to the Awingu environment. To increase security, it is recommended not to use a subdomain of the Awingu environment (e.g. don't use [intranet.awingu.mycompany.com](#) when [awingu.mycompany.com](#) points to your Awingu environment).
- User Labels:** User labels are used in the process of authorizing users to applications. Only users with labels assigned in this field will see the application in the Applications tab (use *all*: to be visible for all users). See chapter on [Label Management](#) for more information.
- Context Policy Labels:** Restrict this application to only be accessible within the provided security context. The context can be configured using the mfa, network or country (2 char ISO 3166-1 alpha code) context policies labels. For network and country, you can define multiple options by using comma-separated values. When adding multiple policies, they must all be valid to be able to access the application. See the [Label Management](#) page for more information and examples.

- **Destination Host Header:** This is the host header passed to the web application. By default, the host of the Destination URL is used. If the web application is configured to accept HTTP requests on the Source Host Header, you can use a custom host header (with the same value of the Source Host Header).
- **Rewrite Content:** Rewrite all URLs in the returned content (HTTP headers and cookies and text/html bodies) from the web application by replacing the host of the Destination URL with the specified Source Host Header. If the web application is configured to accept HTTP requests on the Source Host Header, you may need to disable this feature.
- **Single Sign-On:** If enabled the username and password provided when logging in to Awingu will be passed (base64 encoded) to the Web application in an HTTP authorization header. This requires that the Web application supports basic authentication and is hosted on a Web server with basic authentication enabled.
  - **Authentication Type:** (when Single Sign-on is enabled) defines how the user will be authenticated to the reverse proxied web application
    - Basic Auth: provide the user's credentials to the reverse proxied application using *Basic Authentication*.
    - Remote User: provide the user's username to the reverse proxied web application using the REMOTE\_USER header.
  - **Username field:** (when Single Sign-on is enabled) defines the format of the username used to authenticate the user to the reverse proxied web application using the selected *Authentication Type*
    - Username: use the username without the domain
    - Domain username: use the username prefixed with the domain (e.g. NETBIOS\username)
    - Upn: use the UPN of the user as the username

### Support

- Built-in Reverse Proxy: Rewrite of host headers only works if the URL is clearly present in the body or the headers.
- Unable to make Cross Origin Requests to grouped reverse proxied web applications.
- There is support for websockets for reverse proxied web applications.

### Web Application

Add Web Application

Name

Required

Description

Icon
 No file chosen

Image file (max 100 KB)

Categories

This application will be shown in the selected categories.

Destination URL

The URL of the web application (e.g. https://intranet.company.local, http://172.18.0.2:8080, https://www.youtube.com).

Required

User Labels

The application will only be visible for users with a matching user label. Use "all:" to assign the application to all users; keep empty to have no users assigned.

Advanced Settings

Cancel

Add

- **Destination URL:** Provide the URL on which the website is reachable for the end-user. Make sure the end-user is able to access it.

## Importing applications with a CSV file

When importing a CSV (comma-separated value) file, you can add multiple applications at once. Only RemoteApp is supported.

The CSV file is formatted as follows:

```
"command","name","icon"
"EXCEL","Microsoft Excel 2010","0,0,1,0,5....."
```

### Generating a CSV file

Via a PowerShell script, you can run a script to gather all published RemoteApps on an application server.

1. We provide a sample script on our public GitHub account: [https://github.com/Awingu/awingu-utils/blob/master/RemoteApp/PowerShell/get\\_remoteapps\\_from\\_appserver.ps1](https://github.com/Awingu/awingu-utils/blob/master/RemoteApp/PowerShell/get_remoteapps_from_appserver.ps1). You can download that script with right-click on the Raw button and save the link content.
2. To run the script, which is not signed, you can open PowerShell and execute:

```
powershell -ExecutionPolicy ByPass -File .
\get_remoteapps_from_appserver.ps1
```

3. The script generates the folder Awingu\_Apps in the current working directory containing the CSV file that can be imported in Awingu.

### Importing a CSV file

In Awingu, when importing from file, you can configure for all imported applications following fields:

- Categories
- File Types
- Labels
- Server Labels
- User Labels
- Context Policy Labels
- Auto Start Labels
- Unicode Keyboard Support
- Show in Applications
- Notifications

See [Adding applications manually](#) for more details about those fields. You can always update the afterwards (via Bulk Action).

## Configuring shortcut buttons

For each streamed application, an administrator can configure shortcut buttons that will be provided in a shortcut toolbar to the end user.

Click on the Shortcut Buttons button next to the application name in the list of applications.

Click on Add to create a new key combination:

- **Name:** the text shown on the shortcut button, e.g. Save, Refresh, Next page
- **Key Combination:** text representing the key combination in one of the following formats:
  - modifier + key
  - modifier + modifier + key
  - modifier + modifier + modifier + key

Possible modifiers:

- ctrl
- shift
- alt
- altgr
- windows
- context

Possible keys:

- f1 - f12
- a - z
- 0 - 9
- space
- pageup, pagedown
- end, home
- left, up, right, down
- printscreen
- insert
- delete
- esc
- backspace
- tab
- enter

Note: The Remote Desktop Services Shortcut keys are also available in Awingu. See the User Manual for an overview.



## Application Server Management

- [Introduction](#)
- [Adding/Configuring Application Servers](#)
  - [Importing application servers](#)
  - [Manually adding/editing application servers](#)
- [Further Configuration of the Applications](#)
- [Remote Desktop Connection Broker](#)
  - [Name of the session collection](#)
  - [High availability](#)
  - [Good to know](#)

### Introduction

When an end-user launches a streamed application, a session is set up dynamically between the Awingu appliance and an application server.

The Application Connector (a component within Awingu) will select the application server (hostname and port) that should be used to set up this connection.

In a typical Awingu environment, there are multiple application servers deployed. An application can be served by one or more application servers. However, it is by no means required that each application is installed on every application server.

It is the role of the application connector to find the most suited application server to launch a particular application at a certain moment in time. The default behavior of the Application Connector is:

1. List all application servers where the application is available (based on server labels).
2. Select the server that has the least open connections (known by the Awingu system).
3. If a server is not reachable, another server from step 1 will be selected.

When using a [Application Server Management - Remote Desktop Service Connection Broker](#) (RDS farm), the broker will do the load balancing.

Note: the application servers need to be configured correctly before any streamed application can be opened. Please refer to [Integrating with existing Windows environment](#).

### Adding/Configuring Application Servers

Application servers can be added via System Settings > Manage > Application Servers.

#### Importing application servers

When the bind user has been configured for the domain (see [Domain Settings](#)), you can import them by clicking on **Import from AD** and scroll down.

Note: All application servers that are available in the top-level domain will be shown. Only domain components (dc=) of the Base DN are used.

Import

1. Select Servers

Start typing to search

Name	Host	Dn
AD2012		
AD2012-2		
APP1		
APP2		
APP2008		
APP2008R21		
APP2008R22		
APP2012		
APP2012-1		
APP2012-2		

Items per page 10

1 / 6

2. Set Default Settings

Port 3389

State
 

☒ Enabled
 ☐ Disabled

 Required

Max Connections

Required

Server Labels

Applications with a matching server label will run on the application server. Each new application server will automatically receive a server label named "appserver:<server name>". If the application server is an RDS Session Broker, please use "rdscollection:<collection name>" labels.

Authentication Protocol
 

☒ NTLM
 ☐ Kerberos

- First, select the servers to import. You can use the search box.
- Configure the servers to import:
  - Port:** TCP port used to set up the RDP session to the application server (default 3389).
  - State:** When this attribute is set to 'disabled', no new sessions will be set up to this application server. Toggling from 'enabled' to 'disabled' does not impact active sessions.
  - Max Connections:** Maximum number of simultaneously active RDP sessions that are allowed to this application server. In case this maximum is reached, no new sessions will be set up to this application server. Note: 0 (zero) results in an unlimited number of connections.
  - Server Labels:** Add labels to servers to group them. These groups can be used to assign applications (see also [Application Management](#)) to servers and to filter application servers in lists and reports.
  - Authentication Protocol:** Determines which authentication protocol will be used when connecting to the application server (default NTLM). Normally when selecting Kerberos, you need to provide an authentication host but when you are importing application servers, the authentication host will be set to the host name.

Manually adding/editing application servers

The following attributes can be configured per added application server:

- **Name:** Name of the application server that will be visible in the application connector
- **Host:** Fully qualified domain name or IPv4 of the application server
- **Port:** TCP port used to set up the RDP session to the application server (default 3389).
- **State:** When this attribute is set to 'disabled', no new sessions will be set up to this application server. Toggling from 'enabled' to 'disabled' does not impact active sessions.
- **Max Connections:** Maximum number of simultaneously active RDP sessions that are allowed to this application server. In case this maximum is reached, no new sessions will be set up to this application server. Note: 0 (zero) results in an unlimited number of connections.
- **Description:** Description of the application server (free text format)
- **Server Labels:** Add labels to servers to group them. These groups can be used to assign applications (see also [Application Management](#)) to servers and to filter application servers in lists and reports.
- **Authentication Protocol:** Determines which authentication protocol will be used when connecting to the application server (default NTLM). When Kerberos is selected, an **Authentication Host** (FQDN) of the application server is required.

## Further Configuration of the Applications

Please refer to [Application Management](#) to assign applications to servers and assign applications to users. This page will also allow you to add applications to categories, define the command that needs to be executed, etc.

## Remote Desktop Connection Broker

When using the Microsoft Remote Desktop Connection Broker, only the broker needs to be configured in Awingu. This RD Connection Broker will refer Awingu to the correct application server when opening an application. This means that in the Dashboard, the **broker** that Awingu **initially** connects to will be listed. However, the remote desktop session might end up running on a different RD Session Host.

In this scenario, it's also the RD Connection Broker that load balances the RDP connections between the available RD Session Hosts.

1. Navigate to **System Settings > Manage > Labels**.

Create a label for each RDS Collection configured on the Broker:

- Key: **rdscollection**
- Value: The name of the collection. Mind the pointers below.

2. Navigate to **System Settings > Manage > Application Servers**.

Add the Broker as an application server. In the *Server Labels* field, add the **rdscollection** labels defined in the previous step.

3. Navigate to **System Settings > Manage > Applications**.

In the application's settings, find *Server Labels*. Use the **rdscollection** labels configured in the first step to assign applications to the session collections in which they are published.

### Name of the session collection

Even when the name of an RDS collection has changed at some point, the original name of the collection must still be specified in Awingu. This is because Microsoft Windows Server does not change its collection name internally. To retrieve the original collection name, there are 3 options:

- Check the Windows registry on `HKEY_LOCAL_MACHINE\SOFTWARE\Microsoft\Windows NT\CurrentVersion\Terminal Server\CentralPublishedResources\PublishedFarms\<CollectionName>`
- Check the following folder: `C:\Windows\RemotePackages\CPubFarms\<CollectionName>`
- Download an RDP file via RDWeb and open it in Wordpad. One of the lines is: `loadbalanceinfo:s:tsv://MS Terminal Services Plugin.1.<CollectionName>`

Additionally:

- If the name of the session collection is longer than 15 characters, it must be truncated to 15 characters.
- If the name of the session collection contains spaces, these must be converted to underscores ( \_ ). For example, the name "App Zone A" becomes "App\_Zone\_A".
- If the name of the session collection contains dots, the dots must be removed. For example, the name "App.Zone.A" becomes "AppZoneA".

### High availability

High availability means that end users should still be able to start new remote application sessions, even when one or more servers go down.

It may however take a short period of time before the failover is fully functional.

Existing application sessions will not be resumed.

### Microsoft RD Connection Broker

In this scenario, there are at least two Microsoft Windows servers acting as a **RD Connection Broker**; They point to the same (high-available) SQL database and there's a DNS name for this RD Connection Broker cluster. Only one of those servers is the **RD Management Server (rdms)**. If the management server goes down, a remaining broker automatically takes over this role after a couple of minutes.

Microsoft offers two ways to connect to this high-available environment:

1. By using a **load balancer**. The load balancer is responsible to check whether a server with the RD Connection Broker is reachable. It should also distribute the connections evenly.
2. By using a **round-robin DNS record**: For the DNS name of the RD Connection Broker cluster (for example `rdcb.somewindowsdomain.org`), multiple IP addresses can be resolved.

Once high availability is properly configured on the Microsoft side, it's time to configure Awingu.

### Configuration in Awingu

The configuration in Awingu is based on the first approach, Awingu acts as a load balancer.

For each RD Connection Broker in the cluster, an application server should be added in Awingu with the proper **rdscollection** label assigned to it. The IP address or FQDN of the individual server should be used as hostname. Do **NOT** use the DNS name of the cluster.

Also, ensure high availability for the Awingu cluster by setting up a redundant multi-node environment.

### Which broker will Awingu connect to?

When a user launches an application with a `rdscollection` label attached to it, Awingu builds a list of candidate servers. In this case, this would be the list of the RD Connection Brokers (application servers in Awingu) with the same `rdscollection` label as assigned to the application. Awingu checks if the RD Connection Broker to which it has the least connections is reachable and tries to connect to this host. If it's unreachable, Awingu tries connecting to the next candidate.

When session merge is enabled, Awingu also tries to re-use an existing prior connection if available.

#### Good to know

Sometimes, some administrators opt to define specific RD Session Hosts as an application server in Awingu (using the **appserver** label). However, if those RD Session Hosts are managed by a RD Connection Broker, it's possible the user ended up on a different RD Session Host anyway.

To prevent this, there is a Windows group policy to disable participating in this load-balancing behavior on the Microsoft RDS environment: *Computer Configuration / Administrative Templates / Windows Components / Remote Desktop Services / Remote Desktop Session Host / RD Connection Broker / Use RD Connection Broker Load Balancing*: set to **disabled**.

## Category Management

Categories are logical groups of applications available to end-users. These categories are visible to end-users in the left pane of the Applications tab in the Awingu application. There are three types of categories:

- **Category All:** The category 'All' contains all applications to which the end-user is authorized. This category is always present and cannot be configured, i.e. this category is not visible in the configuration management console.
- **Category Favorite:** When a user first logs on to Awingu, this category is empty. End-users can add/remove applications to the 'Favorite' category. The category 'Favorite' is always visible to end-users in the user interface, even when it is empty. The category 'Favorite' is built-in to the Awingu application and is not configurable by administrators.
- **Other categories:** System administrators can define additional categories for end-users. These additional categories will be visible to end-users when they are authorized to at least one application that belongs to that category. There is a many-to-many relationship between applications and categories. Administrators can assign zero, one or multiple categories to an application, see [Application Management](#). Similarly, a category can be assigned to zero, one or more applications.

This page provides you the list of existing categories and allows you to add, remove or modify categories.

## Drive Management

- [Introduction](#)
- [Supported protocols](#)
- [Adding/editing drives](#)
- [Security](#)

## Introduction

Awingu provides the user with access to file server back ends: CIFS, WebDAV and OneDrive for Business. Browsing files is implemented as a series of REST API calls to the Awingu platform infrastructure. The Awingu platform infrastructure then proxies these REST API calls to another protocol that is supported by the drive back end. Creating, renaming, moving, copying, uploading and downloading files is also possible. Files can also be opened with configured streamed applications (except when using OneDrive): in this case, the application server will mount the user's drive and open the application with the specified file.

## Supported protocols

The current release of Awingu supports the following protocols:

- CIFS with support for:
  - SMB2 and SMB3 (basic) for Windows Server.
  - Samba3 server
- WebDAV with support for:
  - IIS for Windows Server with a minimum requirement of WebDAV class 2.
- [Microsoft OneDrive for Business](#) (see [link](#) for step-by-step instructions to set-up). Note that for OneDrive back ends, the user cannot select "Open with" with a streamed application.

From an end-user perspective, there is no noticeable difference in behavior between the different types of back ends: the same file navigation rules apply to both. It is also possible to move/copy files and directories across file storage back ends.

It is technically possible to create 2 different drives mapping to the same back end, e.g.:

- Drive "Shared folder" maps to `smb://file-server.company.com/Shared/`
- Drive "Project folder" maps to `smb://file-server/company.com/Shared/Sales/Common/Projects/`

In this peculiar case, when an end-user **moves** a file/folder from "Shared folder > Sales > Common > Projects" to "Project folder", Awingu does not take into account this maps on the same folder. The Awingu interface will ask whether to overwrite the moved file/folder, resulting in the file /folder to be deleted (because a move is a copy-overwrite followed with a delete of the original file).

Notes:

- SMB 3.0 Transparent Failover is not yet supported.
- Limited support for Distributed File System (DFS), branching/DFS namespace is not yet supported.

## Adding/editing drives

Drives are configured to allow end users accessing file servers via a web-based file manager. Authorization to drives is done in a similar way as configuring authorization to applications, by means of labels.

- **Name:** Name of the drive as it will be displayed in the Awingu end-user interface, in the left pane of the Files tab.
- **Description:** Free text description of the drive.
- **Backend:** Protocol via which the Awingu API will communicate with the file server back end. Supported protocols:
  - CIFS: also called SMB or Samba
  - WebDAV
  - Microsoft OneDrive For Business. More details [here](#).
- **Client ID:** (only for OneDrive) Client ID (Application ID) of your configured OneDrive Awingu app in Azure.
- **Client secret:** (only for OneDrive) secret created when adding your OneDrive Awingu app to Azure
- **Workspace URL:** (only for OneDrive) the URL a user uses to access Awingu, e.g. <https://awingu.mycompany.com>
- **Redirect URL:** (only for OneDrive) (read/only) URL to use to configure your OneDrive Awingu app in Azure.
- **URL:** URL of the file server that will be used by the Awingu API to communicate with the file server.

Note that this URL can be parameterized with:

- **<username>:** the user's username
- **<domain>:** the name of the domain the user is part of

URL needs to be based on FQDN name, not NetBIOS.

Examples:

- SMB: `smb://file-server.stack.awingu.com/home/<username>/Documents`
- WebDAV: `http://file-server.stack.awingu.com:8080/home/<username>/Documents`

- OneDrive: link to your sharepoint.com environment: `https://mycompany.sharepoint.com`. Note that you should **not** specify a URL with “-my” here; this will result in an error message about too many redirects.
- **UNC:** UNC that will be used by the application server to access the drives. This UNC path is needed when using "Open with" as action on the Files tab in Awingu.

Note that this URL can be parameterized with:

- **<username>**: the user's username
  - **<domain>**: the NETBIOS name of the domain the user is part of
- Example:

```
\\file-server\Home\<username>\Documents
```

UNC needs to be based on NETBIOS name, not FQDN.

If no UNC path is provided, you can only "Open with" preview (if available).

- **Domain Use:** (only for WebDAV) During authentication against the WebDAV file server, it may be required to pass the domain name. This depends on the configuration of the WebDAV file server. If required, check the box **Use Domain** in Awingu. This option is ignored in case of a CIFS file server back end.
- **Authentication Role:** (only for CIFS) Defines how to authenticate with the CIFS server
  - User: authenticate as the user accessing the drive
  - Anonymous: authenticate as an anonymous user (should be enabled on the CIFS server)
- **Labels:** Assign labels to drives to create groups of drives. These groups can be used to select, filter, and report on drives.
- **User Labels:** By assigning user labels to drives, you can grant groups of users access to drives. Only users in user groups assigned to a label will see the drive in the Files tab (use *all:* to be visible for all users). For more information on labels, please consult the section [Label Management](#).
- **Context Policy Labels:** Restrict this drive to only be accessible within the provided security context. The context can be configured using the mfa, network or country (2 char ISO 3166-1 alpha code) context policies labels. For network and country, you can define multiple options by using comma separated values. When adding multiple policies, they must all be valid to be able to access the drive. See the *Label Management* page for more information and examples.

## Security

Awingu acts as a client to the file server. If there is a need to scan uploaded files for malware or block certain file extensions, this should be managed by the file server.

## File Type Management

- [Introduction](#)
- [Linking Application \(or preview action\) to a file type.](#)

### Introduction

File types are the way to link a file on the Awingu Files page to a configured Application. If multiple applications are associated to a file type, the user can choose which one to use.

A selection of common used file types are already configured in Awingu at install time.

The screenshot shows the 'Add File Type' dialog box within the 'Manage' tab of the 'DEV-AWINGU' System Settings. The dialog has a title bar with 'DEV-AWINGU', 'Configure', 'Manage', and 'Changes' tabs, and a 'Global' dropdown. The main content area is titled 'Add File Type' and contains the following fields and sections:

- File Extension:** A text input field with a red border and the label 'Required' below it.
- Description:** A larger text input field.
- Icon:** A section with a question mark icon, a 'Browse...' button, and the text 'No file selected.'
- Apps:** A section with two columns: 'Available items' and 'Chosen items'. Both columns have a search input field with the placeholder 'Start typing to search'. Below the 'Available items' list is a 'Select all' button. Below the 'Chosen items' list is a 'Select all' button. Between the two lists are right and left arrow buttons. The 'Available items' list contains the following items: API Docs, Dashboard, Advanced Insights, Preview, Recorded Session Player, System Settings, Bob50 (app2012) Çœßøÿ #"/(, Microsoft Word (app2008) Çœ, Microsoft Word RDP (app200), and Microsoft Word RDP (app2012).
- Buttons:** 'Cancel' and 'Add' buttons are located at the bottom right of the dialog.

The footer of the dialog shows 'System Settings - © 2012-2018 Awingu N.V. - Eula' and the version '4.1.1'.

### Linking Application (or preview action) to a file type.

When opening files in Awingu, the file type of the file is inspected to determine which applications can be used to open the file.

Four parameters are used to define a file type:

- **File Extension:** This is the part of the file name after the leading dot



- **Description:** Free text description
- **Icon:** Icon used to represent the given file type on the Files page in Awingu.
- **Apps:** List of applications that can be used to read or modify this file type

## Label Management


- [Introduction](#)
- [User Labels](#)
  - [Importing Labels](#)
  - [Example of Use of User Label](#)
- [Server labels](#)
- [Labels](#)
- [Context Policy Labels](#)

## Introduction

Labels in Awingu serve different purposes, There are 4 types of labels.

- User Labels: Assign applications, drives or features to users or groups.
- Server Labels: Assign applications to application servers.
- Labels: Attaching a label to applications or drives allows you to use this label when filtering or querying in the *System Settings* or *Dashboard*.
- Context Policy Labels: Define context requirements for applications, drives, features, login or the admin role.

Note: Creating labels can be done on the *Manage > Labels* page of the *System Settings* or it can also be created on the fly when configuring a resource. See example below.



## User Labels

User labels are used to assign applications, drives or features to users. Each time a user signs-in, labels are assigned to the user based on their LDAP properties. If you add those labels to application, drives or features, users with the matching labels will have access to this applications or drives, or will have this feature enabled.

**i** User Labels need to be created manually or imported (see below). They are not automatically created from the LDAP properties of the logged-in users.

Key	Value	Comments
group	<the name of the security group>*	Custom made user label. Per security group you want to filter on in Awingu, an entry with <i>group</i> key needs to be made. You can use <i>Import groups from AD</i> to find user groups to auto-generate the labels.
username	<username in DOMAIN\username format>*	Custom made user label. Per user name you want to filter on in Awingu, an entry with <i>username</i> key needs to be made. You can use <i>Import users from AD</i> to find user groups to auto-generate the labels. <b>!</b> The domain should be entered in uppercase and username should be entered in lower case, e.g. MYDOMAIN\johndoe
upn	<username in username@fqd-for-upn format>*	Custom made user label. Per user name (via UPN) you want to filter on in Awingu, an entry with <i>upn</i> key needs to be made.
ou	<the name of the organizational unit>*	Custom made user label. Per OU you want to filter on in Awingu, an entry with <i>ou</i> key needs to be made.
all	(empty)	Predefined user label. Do not remove. When this label is attached to a drive/app/feature, all users from that domain, can access that drive/app/feature.
admin	(empty)	Predefined user label. Do not remove. This label corresponds with the groups indicated as <i>admin</i> in the <a href="#">User Connector Configuration</a> .
record	(empty)	Predefined label. Do not remove.

		Add as label to an application (RDP and RemoteApp) to activate <a href="#">application session recording</a> (needs to be enabled).
smartcard	(empty)	Predefined label. Do not remove. Add as label to an application (RDP and RemoteApp) to enable <a href="#">Smart Card Redirection</a> .
state	enabled	Predefined user label. Do not remove (system label).

\* To look-up the *ou*, *group*, *username* or *upn* of users that have already signed in on Awingu, navigate to Manage > Users: select a user to show the properties, including the labels.



When assigning user labels it needs to be taken into account that the labels are case sensitive.

#### Importing Labels

To auto-create *group* and *username* labels, you can use the buttons *Import groups from AD* and *Import users from AD*. To be able to use this feature, the bind user needs to be configured in [Domain Settings](#).

When clicking on the button, the groups/users are listed as shown below:

## Labels

Bulk Action ▾

✓ Key ▴	Value	Actions
✓ admin		
✓ all		
✓ appservergroup	2008	
✓ appservergroup	2012	
✓ record		
✓ smartcard		
✓ staff		
✓ state	enabled	

Items per page 10 ▾

1

Add Manually

Import groups from AD

Import users from AD

### Import Group Labels

#### Select Groups

✓ Name ▴	Dn
✓ Access Control Assistance Operators	CN=Access Control Assistance Operators,CN=Builtin,DC=stack,D...
✓ Access-Denied Assistance Users	CN=Access-Denied Assistance Users,CN=Users,DC=stack,DC=a...
✓ Account Operators	CN=Account Operators,CN=Builtin,DC=stack,DC=awingu,DC=com
✓ Administrators	CN=Administrators,CN=Builtin,DC=stack,DC=awingu,DC=com
✓ Allowed RODC Password Replication Group	CN=Allowed RODC Password Replication Group,CN=Users,DC=s...
✓ Backup Operators	CN=Backup Operators,CN=Builtin,DC=stack,DC=awingu,DC=com
✓ CD Staff	CN=CD Staff,OU=SGO-Users,DC=stack,DC=awingu,DC=com
✓ CDAdmins	CN=CDAdmins,OU=SGO-Users,DC=stack,DC=awingu,DC=com
✓ Cert Publishers	CN=Cert Publishers,CN=Users,DC=stack,DC=awingu,DC=com
✓ Certificate Service DCOM Access	CN=Certificate Service DCOM Access,CN=Builtin,DC=stack,DC=a...

Items per page 10 ▾

1

Cancel

Import

You can use the search box to filter. Select the desired groups/users and click on Import.

#### Example of Use of User Label

We have following AD configuration:

- ou:Europe
  - group:Engineering
  - group:Europe Managers
- ou:America
  - group:Accountancy
  - group:HR
  - group:America Managers
- ou:Global
  - group:Administrators

In [User Connector Configuration](#), we have for this domain:

Domain Administrators	group:Administrators
-----------------------	----------------------

In [Label Management](#), we have added following rows:

Key	Value
ou	Europe
ou	America
group	Engineering
group	Europe Managers
group	Accountancy
group	HR
group	America Managers

In [Drive Management](#), we have added following user labels to the drives:

Drive	Labels
Home Drive	all:
Engineering Drive	group:Engineering
Accountancy Drive	group:Accountancy
Managers Drive	group:Europe Managers group:America Managers
Administrators Drive	admin:

In [Application Management](#), we have added following User labels to the applications:

Application	Labels
Microsoft Word	all:
AutoCad	group:Engineering
Finance Explorer	group:Accountancy
Cost Calculator	group:Engineering

	group:Accountancy
Euro Specs	ou:EMEA group:HR
Network Manager	admin:

This results in this overview of rights:

Domain\user and security groups	Available applications	Available drives
John: ou: Europe groups: Engineering, Europe Managers	- Microsoft Word - AutoCad - Cost Calculator - Euro Specs	- Home Drive - Engineering Drive - Managers Drive
Lucy: ou: Europe groups: Engineering	- Microsoft Word - AutoCad - Cost Calculator - Euro Specs	- Home Drive - Engineering Drive
Maria: ou: Europe groups: Administrators	- Dashboard* - System Settings* - Recorded Session Player* - Microsoft Word - Network Manager - Euro Specs	- Home Drive - Administrators Drive
Kim: ou: America groups: Accountancy, America Managers	- Microsoft Word - Finance Explorer - Cost Calculator	- Home Drive - Accountancy Drive - Managers Drive
Patrick: ou: America Groups: HR, America Managers	- Microsoft Word - Euro Specs	- Home Drive - Managers Drive

\* pre-installed system application

## Server labels

To assign applications to application servers, both the application server and the applications need to have a label in common.

Key	Value	Comments
rdscollection	<the name of the RDS collection>	Custom made server label. See <a href="#">Remote Desktop Service Connection Broker</a> for more information.
<any key>*	<any value>	Custom made server label. Any key* and value can be used to link applications with application servers.

\* Any key, except the reserved ones defined in this document.

## Labels

All labels can be used for filtering in search boxes and reporting tools. Server and user labels can be used for that purpose, too.

Key	Value	Comments
smartcard	(empty)	Predefined label. Do not remove. See <a href="#">Smart Card Redirection</a> for more information.
audioinput	(empty)	Predefined label. Do not remove, nor use (system label).
<any key>*	<any value>	Custom made label. Any key* and value can be used to filter.

\* Any key, except the reserved ones defined in this document.

## Context Policy Labels

These labels allow you to define what security context is required to:

- access an application or drive
- use a feature
- login
- be assigned the admin role

We support 3 types of context labels.

- **country:** the value of this label accepts a single or a comma separated list of 2 char ISO 3166-a alpha codes. See [https://en.wikipedia.org/wiki/ISO\\_3166-1](https://en.wikipedia.org/wiki/ISO_3166-1) for a full list. E.g. 'country:BE' or 'country:BE,NL'
- **network:** the value of this label accepts both a single IP address (e.g. 'network:172.16.0.15') or a subnet (e.g. 'network:172.16.0.0/8'). Multiple networks or IP addresses can be added using a comma separated list.
- **'mfa:required':** this label is automatically created. When Multi-Factor Authentication is not required at login, a dialog will be shown explaining the user he will need to re-login and use MFA to access an application, drive or feature,

When combining different types of context labels, they must all be valid before the user has access to the resource,

E.g. The Context Policy Label 'country:BE,NL mfa:required' means that the user will have access to the resource if his IP address comes from Belgium or the Netherlands AND he logged in using Multi-Factor Authentication.

## User Management

The Awingu System Settings allow administrators to list and filter users. Administrators can also consult more detailed information about a user such as:

- first login date
- last login date
- labels that have been assigned to this user
- email address
- configured locale and keyboard layout

Except for the Keyboard Layout and Locale setting, all parameters are dynamically populated in the database at login into the platform, based on information retrieved from the enterprise authentication infrastructure (AD/LDAP), see also the section [User Connector Configuration](#).

To logout users and close their application session, please refer to [Live Monitoring of Users Activity](#).

## Deleting users

Users can be deleted from Awingu, but as long they exists in an authorized user group on the AD/LDAP, they will be able to sign-in again.

Depending on the license type, deleted users will still be shown until the end of the month (the Deleted column will have a checkmark) or they will be deleted immediately.

STACK

Configure

Manage

Global

Apply Changes

User Details

Name

clybouwy

Date joined

2015-05-20 16:53:13

Last login

2016-02-17 15:30:46

Is staff

false

Is superuser

false

E-mail

Labels

username:STACK\clybouwy

upn:clybouwy@stack.awingu.com

email:

domain:STACK

ou:SGO-Users

guld:fdcddb74-5c28-e743-b218-ef82be08c7e7

accountExpires:

maxPasswordAge:

minPasswordAge:

passwordLastSet:1450270586.0

User profile

RDP gateway

long-living-v2-3-1

Locale

English

Keyboard Layout

French (Belgium)

System Management Console - © 2012-2015 Awingu N.V. - Eula3.1.0



## System Settings - Change Log

For auditing reasons, all system settings are logged and kept during 13 months. This applies both for changes done in the System Settings web interface and for changes done through the [REST API](#).

DEV-AWINGU ▾

Configure ▾

Manage ▾

Changes

Global ▾

### Changes

Filters

Action ▾

Resource type ▾

Resource id

User ▾

Authentication ▾

From

To

Reset

	Action	Resource Type	Resource Id	User	Authentication	Timestamp
✓	Update	App	DEV-AWINGU - Micr...	dev-awingu\lopeza-a...	Session	2018-12-07 14:30:28
✓	Update	App	DEV-AWINGU - Micr...	dev-awingu\lopeza-a...	Session	2018-12-07 14:30:21
✓	Update	App	DEV-AWINGU - Micr...	dev-awingu\lopeza-a...	Session	2018-12-07 14:29:51
✓	Update	Domain	DEV-AWINGU	admin	Session	2018-12-07 09:57:55
✓	Update	Domain	DEV-AWINGU	admin	Session	2018-12-07 09:52:24
✓	Update	Two Factor Provider	DEV-AWINGU - RAD...	admin	Session	2018-12-07 09:52:24
✓	Update	App	DEV-AWINGU - Micr...	admin	Session	2018-12-06 15:04:40
✓	Update	App	DEV-AWINGU - Micr...	dev-awingu\lopeza-a...	Session	2018-12-06 12:52:13
✓	Update	Configuration	Configuration	dev-awingu\yannick-...	Session	2018-11-28 11:33:12
✓	Update	Configuration	Configuration	dev-awingu\yannick-...	Session	2018-11-28 11:24:51

10 items per page

1 / 29

Export CSV

System Settings - © 2012-2018 Awingu N.V. - Eula4.1.1

If you are an admin of an administrative domain (global admin) or logged in with the management user (set-up during installation)

- You can select the domain you want to see the changes of with the domain drop-down on the top left
- You can see all global changes, regardless of the selected domain.

If you are a domain admin (non-administrative domain), you will only see changes of your domain. You can export the queried results to a CSV file.

You can filter and list the changes for following fields:

- **Action:** Create / Delete / Update
- **Resource type:** Those are the resources used in the REST API. They mostly map with the corresponding pages of the System Settings.
- **Resource Id:** This is typically the name of the resource, e.g. name of the application, user group, label, etc.
- **User:** User who performed the change.
- **Authentication:** Whether a session (username/password) or API token (see [User Connector Configuration](#)) has been used.
- **Timestamp:** Date and time when the change was made.

When clicking on a change in the list, the body of the REST API request and response is shown, even when the change has been done trough the web interface. Example for action *Update*, resource type *Contact*, the change log when editing the phone number of the partner on the General Info page:

- Request:

```
{  
  "phoneNumber": "+9876543210"  
}
```

- Response:






```
{  
  "name": "My Awingu Partner",  
  "location": "East-Flandres",  
  "uri": "http://172.16.5.65/api/v2/contacts/1/",  
  "city": "Gent",  
  "phoneNumber": "+9876543210",  
  "addressLine1": "Some street 1",  
  "country": "Belgium",  
  "postalCode": "9000",  
  "addressLine2": ""  
}
```

# Service Provider Support in Awingu

## Introduction

Awingu allows service providers to give access to applications and documents to their customers in a secure way.

We will describe 5 possible use cases:

	Number of Awingu environments	Number of Awingu domains	Number of Windows domains	Branding per customer
1	One	One	One	
2	One	Multiple (one per customer)	One	
3	One	Multiple (one per customer)	Multiple (one per customer)	
4	Multiple (one per customer)	One per Awingu	One	
5	Multiple (one per customer)	One per Awingu	Multiple (one per customer)	

A service provider can combine those use cases, e.g. 1 Awingu environment for multiple small customers and multiple Awingu environments for some of the bigger clients.

For automatic configuration, Awingu offers an API (see [Automate Awingu via the REST API](#)).

When using a multi-node high available deployment, we strongly recommend doing the SSL offloading at the load balancer.

## Case 1: One Awingu / One Awingu Domain / One Windows Domain

## Architecture

Access to Awingu:

- All customers access Awingu via the same URL, e.g. <https://www.provider.com>
- All customers will see the same branding.

For the Awingu topology, the following is required

- Multi-node setup (for +100 concurrent users)
- External load balancing (for high availability or +200 concurrent users)
- External database (for high availability or +200 concurrent users)

The Windows architecture:

- Only 1 domain with one or multiple domain controllers, file servers and application servers.
- The users of a customer are grouped in the same organizational unit (OU) or security group.

## Licensing

Only 1 Awingu license is needed for the desired number of maximum concurrent users.

## Configuration

- System Settings > Global > Domain:
  - Define 1 domain.
  - This domain should be an *Administrative domain*.
  - Provide a bind user to allow import.
- System Settings > Configure > User Connector:
  - Define the group(s) that need administrator rights
  - Assign the *Admin* user group label to it
- System Settings > Manage > Labels:
  - In case customers are grouped per OU: create a label per customer:
    - Key: *ou*
    - Value: the name of the OU (case sensitive)
  - In case customers are grouped per security group: use *Import groups from AD*
- System Settings > Manage > Application Servers: define or import the application servers for that domain.
- System Settings > Manage > Applications: define the applications and limit the usage per customer with the ou/group labels.
- System Settings > Manage > Drives: define the drives and limit the usage per customer with the ou/group labels.
- System Settings > Configure > Features: you can limit some features per customer with the ou/group labels.
- System Settings > Configure > Branding: you can only define one branding.

## Administration

Only the service provider will be able to manage Awingu. There is no multi-tenancy in this case.

### Case 2: One Awingu / Multiple Awingu Domains / One Windows Domain

## Architecture

Access to Awingu:

- You can define multiple DNS entries pointing to Awingu in order to give each customer his own URL, e.g. <https://customer1.provider.com>. If you access Awingu via an unknown host header (or via IP address), you can enter your domain manually (if not provided, the default domain will be used).
- You can define branding for each customer.

For the Awingu topology, the following is required

- Multi-node setup (for +100 concurrent users)
- External load balancing (for high availability or +200 concurrent users)
- External database (for high availability or +200 concurrent users)

The Windows architecture:

- Only 1 domain with one or multiple domain controllers, file servers and application servers.
- The users of a customer are grouped in the same organizational unit (OU) or security group.

## Licensing

Only 1 Awingu license is needed for the desired number of maximum concurrent users. You can limit the number of concurrent users per domain.

## Configuration

- System Settings > Global > Domain:
  - Define a domain for the employees of the service provider. That domain should be an *Administrative Domain* and should be the *Default* domain.

- Define 1 domain per customer. Those domains should **not** be *Administrative Domains*. The *NetBIOS Name* is the same for each customer, but the *Name* is different.
- Per customer domain: provide the Host Header, e.g. customer1.provider.com
- Per customer domain: provide a bind user to allow import.
- Per customer domain: define the maximum concurrent users, if desired.
- In case customers (or the employees of the service provider) are grouped per OU: limit access via the *Base DN*, e.g. "ou=Customer 1, dc=provider,dc=com"
- Per Domain (select via the top left):
  - System Settings > Configure > User Connector:
    - User Groups:
      - In case customers (or the employees of the service provider) are grouped per security group:
        - Define the group which should have access.
      - Define the group which needs administrator rights:
        - For the domain of the service provider: members of that group can manage all domains and the global settings. Those are Global Admins.
        - For the domain of a customer: members of that group can manage the domain (applications servers, applications, drives, features, branding, etc). As all customers share the same Windows domain, it is not recommended to allow customers themselves to manage their domain. It makes more sense that the assigned solution engineers of the service provider are managing the domain. Those are Domain Admins.
    - User Group Labels:
      - Assign the *Admin* label to the defined administrator group
  - System Settings > Manage > Application Servers: define or import the application servers for that domain.
  - System Settings > Manage > Applications: define the applications for that domain.
  - System Settings > Manage > Drives: define the drives for that domain.
  - System Settings > Configure > Features: you can limit some features for that domain.
  - System Settings > Configure > Branding: you can define the branding for that domain.

## Administration

Global Admins:

- Are the members of the Admin group defined for the domain of the service provider.
- Can manage all domains and global settings.

Domain Admins:

- Are the members of the Admin group defined for a customer domain.
- Can only manage applications, drives, features, branding etc. of that customer.

The Dashboard is only available for Global Admins.

### Case 3: One Awingu / Multiple Awingu Domains / Multiple Windows Domain

## Architecture

Access to Awingu:

- You can define multiple DNS entries pointing to Awingu in order to give each customer his own URL, e.g. <https://customer1.provider.com>. If you access Awingu via an unknown host header (or via IP address), you can enter your domain manually (if not provided, the default domain will be used).
- You can define branding for each customer.

For the Awingu topology, the following is required

- Multi-node setup (for +100 concurrent users)
- External load balancing (for high availability or +200 concurrent users)
- External database (for high availability or +200 concurrent users)

The Windows architecture:

- Each customer has his own domain with one or multiple domain controllers, file servers and application servers.
- The employees of the service provider will typically have their own domain, too.

## Licensing

Only 1 Awingu license is needed for the desired number of maximum concurrent users. You can limit the number of concurrent users per domain.

## Configuration

- System Settings > Global > Domain:
  - Define a domain for the employees of the service provider. That domain should be an *Administrative Domain* and should be the *Default* domain.
  - Define 1 domain per customer. Those domains should **not** be *Administrative Domains*. The *NetBIOS Name* will be typically equal to the *Name* of the domain.
  - Per customer domain:
    - Provide the Host Header, e.g. [customer1.provider.com](https://customer1.provider.com) . This is the host header for the Awingu workspace for this customer.
    - Provide a bind user to allow import users from the LDAP server.
    - Define the maximum concurrent users, if desired.
- Per Domain (select via top left):
  - System Settings > Configure > User Connector:
    - User Groups: define the group which needs administrator rights:
      - For the domain of the service provider: members of that group can manage all domains and the global settings. Those are Global Admins.
      - For the domain of a customer: members of that group can manage the domain (applications servers, applications, drives, features, branding, etc). Typically, members of that domain are the IT administrators of the customers and/or the solution engineers of the service provider. Those are Domain Admins.
    - User Group Labels:
      - Assign the *Admin* label to the defined administrator group
  - System Settings > Manage > Application Servers: define or import the application servers for that domain.
  - System Settings > Manage > Applications: define the applications for that domain.
  - System Settings > Manage > Drives: define the drives for that domain.
  - System Settings > Configure > Features: you can limit some features for that domain.
  - System Settings > Configure > Branding: you can define the branding for that domain.

## Administration

Global Admins:

- Are the members of the Admin group defined for the domain for the service provider.
- Can manage all domains and global settings.

Domain Admins:

- Are the members of the Admin group defined for a customer domain.
- Can only manage applications, drives, features, branding etc. of that customer.

The Dashboard is only available for Global Admins.

### Case 4: Multiple Awingus / One Awingu Domain per Awingu / One Windows Domain

## Architecture

Access to Awingu:

- Each Awingu environment has its own IP address and DNS entry. Each customer has his own URL, e.g. <https://customer1.provider.com>.
- You can define branding for each Awingu.

For the Awingu topology, the following is required

- Multi-node setup for each customer with +100 concurrent users.
- External load balancing for each customer requiring high availability or +200 concurrent users.
- External database for each customer requiring high availability or +200 concurrent users. The same database server(s) can be shared for multiple customers.

The Windows architecture:

- Only 1 domain with one or multiple domain controllers, file servers and application servers.
- The users of a customer are grouped in the same organizational unit (OU) or security group.

## Licensing

You need an Awingu license for each Awingu (customer), each one for the desired number of maximum concurrent users.

## Configuration

- Per Awingu environment:
  - System Settings > Global > Domain:
    - Define 1 domain.
    - This domain should be an *Administrative domain*.
    - Provide a bind user to allow import.
    - In case customers are grouped per OU: limit access via the *Base DN*, e.g. "ou=Customer 1,dc=provider,dc=com"
  - System Settings > Configure > User Connector:
    - User Groups:
      - In case customers are grouped per security group:
        - Define the group which should have access.
      - Define the group which needs administrator rights: members of that group can manage that Awingu environment. As all customers share the same Windows domain, it is not recommended to allow customers themselves to manage their Awingu environment. It makes more sense that the assigned solution engineers of the service provider are managing the Awingu environment.
    - User Group Labels:
      - Assign the *Admin* label to the defined administrator group
  - System Settings > Manage > Application Servers: define or import the application servers for that Awingu environment.
  - System Settings > Manage > Applications: define the applications for that Awingu environment.
  - System Settings > Manage > Drives: define the drives for that Awingu environment.
  - System Settings > Configure > Features: you can limit some features for that Awingu environment.
  - System Settings > Configure > Branding: you can define the branding for that Awingu environment.

## Administration

Each Awingu environment can be fully managed by the members of the Admin group defined for each environment.

### Case 5: Multiple Awingus / One Awingu Domain per Awingu / Multiple Windows Domains

## Architecture

Access to Awingu:

- Each Awingu environment has its own IP address and DNS entry. Each customer has his own URL, e.g. <https://customer1.provider.com>.
- You can define branding for each Awingu.

For the Awingu topology, the following is required

- Multi-node setup for each customer with +100 concurrent users.
- External load balancing for each customer requiring high availability or +200 concurrent users.
- External database for each customer requiring high availability or +200 concurrent users. The same database server(s) can be shared for multiple customers.

The Windows architecture:

- Each customer has his own domain with one or multiple domain controllers, file servers and application servers.

## Licensing

You need an Awingu license for each Awingu (customer), each one for the desired number of maximum concurrent users.

## Configuration

- Per Awingu environment:
  - System Settings > Global > Domain:
    - Define 1 domain.
    - This domain should be an *Administrative domain*.
    - Provide a bind user to allow import.
  - System Settings > Configure > User Connector:

- User Groups: define the group which needs administrator rights. Members of that group can manage that Awingu environment.  
Typically, members of that domain are the IT administrators of the customers and/or the solution engineer(s) of the service provider.
- User Group Labels: assign the *Admin* label to the defined administrator group
- System Settings > Manage > Application Servers: define or import the application servers for that Awingu environment.
- System Settings > Manage > Applications: define the applications for that Awingu environment.
- System Settings > Manage > Drives: define the drives for that Awingu environment.
- System Settings > Configure > Features: you can limit some features for that Awingu environment.
- System Settings > Configure > Branding: you can define the branding for that Awingu environment.

## Administration

Each Awingu environment can be fully managed by the members of the Admin group defined for each environment.



# Monitoring and Reporting

## Introduction

The **Dashboard** can be found in Applications. You need to be signed in as a user belonging to a user group labeled as *admin*.

- [Status Overview of Services on All Servers](#)
- [Monitoring Servers and Components](#)
- [Awingu License Tracking](#)
- [Live Monitoring of Users Activity](#)
- [Monitoring the Application Connector](#)
- [Insights Reporting](#)
- [Audit Reporting](#)
- [Anomaly Reporting](#)

## Status Overview of Services on All Servers

The **Status** tab of the Dashboard provides a heat map of servers (vertical axis) versus components (horizontal axis). This tab is only available for admins of an administrative domain (global admins) and the management user (defined at installation).

The following color code convention is adopted:

- Empty: The corresponding component is not installed on this server.
- Dark gray: The component is installed but no data are available.
- Green: The corresponding component is running on the server.
- Orange: One of the corresponding sub components is installed, but not running on the server
- Red: The corresponding component is installed but not running on the server.

Clicking on a component bubble will lead you to a detailed page with more information on the particular component on that server.

Clicking on a server will lead you to a detailed page with more information on the server.

## Monitoring Servers and Components

From the **Servers** tab in the Dashboard, system administrators can obtain more detailed information on servers and processes. This tab is only available for admins of an administrative domain (global admins) and the management user (defined at installation).

On the servers tab a list of servers is presented, together with hostname and status. Clicking on a server leads you to a detailed page with statistics and components.

Statistics are shown over a configurable time interval for the following parameters:

- Memory Usage
- CPU Usage
- Status Information (running/halted)
- Disk Usage

All components/processes installed on that server are also shown with the following attributes:

- Name of component
- IP address
- Port
- Status

Clicking on a component leads you to a page with more details on the component.

## Awingu License Tracking

Awingu provides system administrators the means to track license consumption, as part of the Dashboard. The following metrics are shown:

- Number of named users.
- Number of concurrent user sessions. The "Concurrent User Count" field in your Awingu license (see [General Information](#)) is the maximum value allowed for this metric.

This tab is only available for admins of an administrative domain (global admins) and the management user (defined at installation).

### Number of Named Users

This metric tracks the number of named users on the Awingu platform on a calendar month basis. The graph shows the number of named users for the past 12 months as well as for the current month.

All named users known to Awingu (list visible on the **System Settings > Manage > Users** page) for a given month will count towards this metric, even if the user did not login to Awingu.

The graph and metric is not updated real-time, but twice a day.

### Deleting Users

Users can be deleted on the **System Settings > Manage > Users** page. Depending on the license type, deleted users will still be shown and counted towards the named users metric until the end of the month (the Deleted column will have a check mark) or they will be deleted immediately.

For users that have been removed from Awingu, an entry will be re-created at next login time.

### Peak Number of Concurrent User Sessions

This metric tracks the peak number of browsers signed-in to Awingu on a calendar month basis. It shows the number of concurrent user sessions for the past 12 months as well as for the current month. For the current calendar month, the value is peak number of concurrent sessions up to the current date.

The "Concurrent User Count" field in your Awingu license (see [General Information](#)) is the maximum value allowed for this metric. The management user, created during installation, does not count as concurrent user.

Note that the values are not updated real-time, but every 5 minutes.

### Example

Please follow this example on how the data for the license graphs are generated:

Time stamp	Action	Named Users	Concurrent User Sessions
2019-01-01 09:00	Awingu is just installed	0	0
2019-01-01 10:00	Ada signs-in and opens the streamed app Word	1	1
2019-01-01 10:01	Youssef signs-in and opens the streamed apps Word and Excel	2	2
2019-01-01 10:03	Ada signs-out without closing Word (app is disconnected)	2	1
2019-01-01 10:04	Ada signs-in on other device and recovers the Word app	2	2
2019-01-01 10:05	Youssef closes Word and Excel and signs-out	2	1
2019-01-01 10:06	Ada closes Word and signs-out	2	0
2019-01-01 10:07	Wong signs-in	3	1
2019-01-01 10:08	Wong signs-out	3	0
January 2019	Resulting graphs (peak)	3	2

## Live Monitoring of Users Activity

The **Activity** page in the Dashboard gives administrators insights in the current usage of the platform and allows them to logout users, terminate and view their application sessions.

More specifically, it gives information regarding the number of simultaneous connected browsers to the platform, a.k.a. the number of concurrent users.

Admins of an administrative domain (global admins) and the management user (defined at installation) can filter for specific domains with the dropdown on the top left. Domain admins only see users of their domain.

- **Total active concurrent user sessions:** counts the number of currently connected concurrent users.
- **Total disconnected user sessions:** counts the number of user sessions that have not been properly closed. This can happen when a user closes the browser without logging out of Awingu or when the battery of the end-user device fails, or when the end-user experiences a connectivity glitch. In those cases, the sessions remain in the **disconnected** state for 10 up to 15 minutes. The list is refreshed at a 5 minute interval.

The table below provides more details regarding the individually connected users:

- Each row represents a user session.
- Per user session, it is possible to see the session ID, the start time of the session, the disconnect time of the session (if applicable), the country and the current status.
- Each user session can be individually logged out.
- Per user session, the linked application sessions can be shown by clicking the view details button (+ icon) on the left.
- Per application session, it is possible to see the application session ID, the application name, the start and end time, the used application server, whether the session was recorded and the status.
- Following actions can be performed on an application session:
  - View session (eye icon): A new browser tab will be opened and after the user of the application session accepts the join request, the admin will be able to view the application session. The admin can also ask keyboard and mouse control of the application session and provide support if necessary.
  - Terminate: The application session will be forcefully terminated and all unsaved changes will be lost.

Note that the countries shown in the table are based on a static geo IP database defined during installation or the last upgrade. Those locations might not be accurate anymore.

## Monitoring the Application Connector

From the **Application Overview** tab in the Dashboard, system administrators can obtain information about applications and application servers.

Admins of an administrative domain (global admins) and the management user (defined at installation) can filter the views for specific domains with the dropdown on the top left. Domain admins only see content of their domain.

### Application Servers

For each server, one can see the number

- active sessions: active applications streamed to the end users
- reserved sessions: a session is reserved when a user requests to open a streamed application. When the application is actually started, the session is not *reserved* anymore, but *active*.

Note that the sum of the active and reserved sessions cannot be higher than *Max Connections* defined for that application server.

### Applications

For each streamed application, one can click through the application insights, showing:

- the number of unique users that used the application (monthly)
- the maximum concurrent usage of the application (monthly)
- how many time each user has used the application

The data can be filtered with the date picker on the top.

## Insights Reporting

The Insights tab contains some overall information about the usage of Awingu. Admins of an administrative domain (global admins) and the management user (defined at installation) can filter for specific domains with the dropdown on the top left. Domain admins only see users of their domain.

### Application Usage

The table shows the number of distinct named users that have been using a particular streamed application over a configurable time interval.

### OS and Browser

This page provides 2 tables that show information about the **end-user device OS** and **browser usage** over a configurable time interval. Every browser session is counted. So for example, if a user has signed-in 20 times during the specified time interval, this will count as 20 sessions in both pie charts.

## Audit Reporting

The Audit reporting tab in the Dashboard provides system administrators further insights in the usage of the Awingu system. Admins of an administrative domain (global admins) and the management user (defined at installation) can filter for specific domains with the dropdown on the top left. Domain admins only see users of their domain.

All data is kept for 13 months. The output can be exported to CSV.

Note: The date/time is shown in UTC.

### Query Syntax

On each page, the admin can query and/or change the date period to limit the shown output.

Examples of query strings:


Query	Expected result
john	All records containing the full word "john"
john*	All records containing a word starting with "john"
*john*	All records containing "john" anywhere
john alice	All records containing the full words "john" or "alice"
john AND alice	All records containing the full words "john" and "alice"
NOT john	All records not containing the full word "john"
@timestamp:{2018-05-02T19:00 TO 2018-05-02T20:00}	All records with timestamp between given times

### Advanced Querying

Using *advanced query* you can use a DSL (Domain Specific Language) to perform more fine-grained filtering.

To enable advanced querying, make sure you tick the 'advanced query' box on the right-hand side of the filter input:

☐ advanced query 

The field names to use in a query are different from the column names in the view. To get an overview of the field names available for the current view, click on the  icon next to *advanced query*.

Below an example of view specific information for *Shared Application Session Settings* audit logs



## Filtering

The basic filter syntax for a comparison of a field to a value is as follow

[field] ([negation]) [filter operator] [value]

The *field* is the name of field to be queried. The *value* is the value the field shall be compared to. Values for strings and timestamps need to be quoted in single quotes. For boolean fields the values *true* and *false* are valid.

The possible values for the *filter operator* are listed in the table further below. Some of these filters can be negated with the optional keyword *not*, to see which operators support negation also see the table below.

Filter operator	Alias	Meaning	Negatable with "not"	Field type requirements
-----------------	-------	---------	----------------------	-------------------------



=	eq	"equal to"	= is not, but the eq alias is negatable	-
!=	not eq	"not equal to"	no	-
<	lt	"less than"	no	-
>	gt	"greater than"	no	-
<=	lte	"less than or equal to"	no	-
>=	gte	"greater than or equal to"	no	-
contains		substring search (case sensitive)	yes	requires text or char fields
icontains		substring search (case insensitive)	yes	requires text or char fields
startswith		substring search at the beginning of the field value (case sensitive)	yes	requires text or char fields
istartswith		substring search at the beginning of the field value (case insensitive)	yes	requires text or char fields
endswith		substring search at the end of the field value (case sensitive)	yes	requires text or char fields
iendswith		substring search at the end of the field value (case insensitive)	yes	requires text or char fields
isnull		value must be NULL	yes	-

## User Sessions

The user sessions show a list of sessions with following information:

Property	Meaning
Start	The start date/time of the Awingu session (when logging on to Awingu)
End	The end date/time of the Awingu session (at disconnect or at logout)
Domain	The Awingu domain of the user
User Session Id	The internal user session id, which can be used to filter on the other audit pages.
Ip	The IP address of the machine which started the Awingu session
Username	The domain\username
Mfa	Whether Multi-Factor Authentication was used or not when logging in.
Latitude	Latitude coordinate/ based on geo IP (which is indicative).
Longitude	Longitude coordinate/ based on geo IP (which is indicative).
Labels	All (user) labels fetched from the AD/LDAP

## Application Sessions

This only applies for streamed applications (RDP and RemoteApp).

Property	Meaning
Start	The start date/time of an application session
End	The end date/time of an application session
Domain	The Awingu domain of the user opening the application

Client Session Id	The internal id for the connection between browser and Awingu*
Application Session Id	The internal id for the connection between Awingu and application servers
User Session Id	The User session id (cf. User Sessions)
Client Session Numeric Id	Short version of the Client Session Id*
Application Key	The internal Awingu id for application (cf. Application Overview > Applications)
Server	The DNS or IP address of the application server
Port	The server port used to connect to the application server
Exe	The alias of the RemoteApp (empty for RDP applications)
Recorded	Whether the application sessions has been recorded.

\* This id changes at each time the session is taken over on another device or in another browser tab.

## Correlate with the logs on the application server

If you want to correlate an application session in Awingu with an RDP session on application server, for that application session, you need to find the oldest log entry. The Client Session Numeric Id corresponding to that entry is the one used at startup of that application session.

This Client Session Numeric Id can be found on the application server **during the connection**:

- Windows Task Manager:  
On the Users tab, the column "Client name" (not shown by default) contains the Client Session Numeric Id (prefixed with AW-)

This Client Session Numeric Id can be found on the application server **post mortem**:

- In the Event Viewer, go to Windows Logs > Security. Click on "Find..." in the right column to search for the Client Session Numeric Id (prefixed with "AW-").  
The event has following properties:
  - Keywords: Audit Success
  - Source: Microsoft Windows security auditing
  - Task Category: Logon

## Shared Application Sessions

The Shared Application Sessions view lists all guests that joined a shared application session.

Property	Meaning
Start	Timestamp on which the client joined the shared application session
End	Timestamp on which the client joined the shared application session
Client Session Id	The internal id for the connection between browser (guest) and Awingu
Client Session Numeric Id	The internal id for the connection between browser (host) and Awingu (is equal to the Client Session Numeric Id of the host of the application session)
IP	The IP address of the client that joined the shared application session

\* Is equal to the Client Session Numeric Id of the host of the application session

## Share Application Sessions Settings

The Shared Application Sessions Settings view lists all shared application sessions and their settings (changes).

Property	Meaning
Timestamp	The timestamp on which the settings where applied
Domain	The Awingu domain of the user opening the application
Client Session Id	The internal id for the connection between browser (guest) and Awingu
Application Session Id	The internal id for the connection between Awingu and application servers

User Session Id	The User session id (cf. User Sessions)
Joinable	Can users join the session
Is Protected	Is a password required to join the session
Join Mode	How is the session shared (SINGLE or MULTI)
Access Rights	How are access rights determined? (PUBLIC, DOMAIN or USER)

## Web Applications

The Web Applications view lists all web applications accessed through Awingu:

- For all web applications, each time a user clicks on the application within Awingu, this is logged.
- For a reverse proxied web application, we also log when the user browses directly to the configured source host header, but the session cookie is not valid anymore. This is the case when the user has logged out from Awingu since the last visit of the web application.

Property	Meaning
Timestamp	Timestamp on which the user has opened the web application
Domain	The Awingu domain of the user opening the web application
User Session Id	The User session id (cf. User Sessions)
Name	Name of the Web Application
Url	Destination URL of the Web Application (connection between Awingu and web server)
Behind Reverse Proxy	Whether the built-in reverse proxy is used for the web application

## IdP Sessions

Only applicable if Awingu is configured to be used a Identity Provider for Single Sign-On (SSO)

Property	Meaning
Login Time	Timestamp an external SSO Service requests Awingu to identify a user
Domain	The Awingu domain of the user opening the web application
Service Provider Name	Name of the service provider, as mentioned in <a href="#">User Connector Configuration</a>
Username	The username
User Session Id	The User session id (cf. User Sessions)
Assertion Customer Service	ACS URL, as configured for the SSO service
Request Issuer	Issuer, as configured for the SSO service
Request Id	SAML request ID, provide by the SSO service

## Shares

The Shares view lists the creation, update, access and deletion of all shares.

Property	Meaning
Timestamp	Timestamp of the log entry
Domain	The Awingu domain of the user that created the share
User Session Id	For create/update/delete: the User session id (cf. User Sessions) performing the action For access: the User session id (cf. User Sessions) accessing the share*
Ip	IP address of the client that created/updated/deleted/accessed the share

country	Country based on geo IP for the listed IP address
Action	Can be create, update**, access or delete.
Name	Name of the share
Drive	Drive from which the file/folder was shared
Path	File path of the shared file/folder
Content Type	Content type of the share
Created By	Username of the user that shared the file
Expires	Expiration date of the share
Id	Internal ID of the share
Folder	Indicates if the share is a folder
Public	Indicates if the share is publicly accessible
Mode	Mode in which the file was shared (DOWNLOAD or PREVIEW)
Checsum	Checksum of the shared file (when accessed)
Range	Range accessed during request***

\* Anonymous access of a public share leads to an empty value.

\*\* A share is updated when a property (e.g. Expiry date/time) has changed or the content has been updated (via Update button in end-user UI).

\*\*\* A single access to a shared *preview* document can lead to multiple entries in the list. When viewing the document, this can be downloaded in multiple chunks into the PDF reader, leading to multiple requests and entries. This allows you to see if a document was downloaded entirely or not.

## Files

The Files view lists all file actions using Awingu. Note that in-app file actions can not be audited, because this happens directly between the application server and the file server. Only actions invoked in the Workspace and Files page can be tracked via Awingu.

Property	Meaning
Timestamp	Timestamp of the log entry
Domain	The Awingu domain of the user that performs the file action
User Session Id	The User session id (cf. User Sessions)
Action	The performed file action, e.g. copy, move*, create folder, upload, ...
Drive	The drive where the file is located
File Path	The path where the file is located
Destination Drive	In case of copy or move: the drive where the file has been copied/moved to
Destination File Path	In case of copy or move: the path where the file has been copied/moved to

\* Renames are treated as moves, where the destination file path is showing the new name.

## Anomaly Reporting

The Anomalies reporting tab in the Dashboard provides system administrators insight in unusual activities on the Awingu environment.

Admins of an administrative domain (global admins) and the management user (defined at installation) can filter for specific domains with the dropdown on the top left. Domain admins only see users of their domain.

The admin can query and/or change the date period to limit the shown output, which can be exported to CSV. The query syntax is the same as for [Audit Reporting](#).

Following anomalies are reported:

Code	Category	Description
COUNTRY_MISMATCH	LOGIN	Same user is logged in in 2 different countries simultaneously
TRAVEL_SPEED	LOGIN	The distance between 2 logins is too far to travel at realistic speed
TOO_MANY_FAILED_ATTEMPTS	LOGIN	A user uses the wrong password more than 3 times
NEW_BROWSER	LOGIN	A user logs in with a new browser
CONTEXT_RESTRICTION	CONTEXT	A user tried to perform an action that was prohibited due to context restrictions

For each detected anomaly, following information is provided:

Property	Meaning
Timestamp	Timestamp of the detected anomaly (UTC)
Domain	Domain of the user
Category	Only LOGIN and CONTEXT categories are supported by now
Code	Type of anomaly (see table above)
Description	More details of the actual anomaly
Ip	IP address of the user
Users Session Id	Users Session Id in case the user logged in (see <a href="#">Audit Reporting</a> )
Username	domain\username

### Country mismatch anomaly

At each login, we identify the country of the user based on his IP address. If a user is logged in simultaneously in two or more different countries, a COUNTRY\_MISMATCH anomaly will be logged. The description field will mention the detected countries.

Note: this can also occur for instance if the user connects to a VPN service where the network traffic suddenly passes through a remote location (for instance headquarters), after already being connected to Awingu.

### Travel speed anomaly

At each login, we identify the location of the user based on his IP address. If the distance of a user between the last logout and the current successful login would imply that the user would travel at a speed of more than 1000 km/h, a TRAVEL\_SPEED anomaly will be logged. The description field will mention the distance and calculated speed in metric and imperial units.

Note: this can also occur for instance if the user connects to a VPN service where the network traffic suddenly passes through a remote location (for instance headquarters), after already being connected to Awingu.

### Too many failed attempts anomaly

When a user fails 3 times consecutively to login, because of a wrong password or a wrong MFA (Multi Factor Authentication) attempt, a TOO\_MANY\_FAILED\_ATTEMPTS anomaly will be logged. The description field will mention the number of consecutive failed attempts.

Note: if a user has never logged in to Awingu before, the anomaly won't be logged.

## New browser anomaly

When a user logs in for the first time to Awingu on a certain browser, a fingerprint is calculated to identify the browser. This fingerprint is stored locally in the browser. At each successful login, that fingerprint is sent to Awingu and if the fingerprint is different from the one of the previous successful login, a NEW\_BROWSER anomaly is logged. The description field will mention the fingerprint.

To calculate the fingerprint, different parameters are taken into account, like user agent, language, screen resolution, time zone etc. If one of those parameters changes, the fingerprint will not be recalculated as long the previous fingerprint is still stored locally in the browser. If the user however clears the local storage of the browser, the fingerprint will be recalculated and an anomaly will be logged.

## Integration

- Integrating with existing Windows environment
- Using Awingu on existing Citrix infrastructure
- SSL offloader, reverse proxy or loadbalancer settings
- Multi Factor Authentication
- Awingu Single Sign On (SSO)
- Microsoft OneDrive for Business
- Smart Card Redirection
- Automate Awingu via the REST API
- External Audit Logging

## Integrating with existing Windows environment

- [Introduction](#)
- [Using the Active Directory Server as NTP server](#)
- [Organizational Units for users and application servers](#)
- [Group Policy recommendations](#)
  - [GPOs for the Awingu users](#)
  - [GPOs for the application servers](#)
- [Set-up Drives connectivity](#)
  - [CIFS connectivity:](#)
  - [WebDAV drives:](#)
    - [To set-up WebDAV via IIS \(version 8\)](#)
    - [WebDAV support for large files](#)
    - [WebDAV adding MIME Type](#)
    - [WebDAV create default MIME type](#)
- [Set-up the Application Servers](#)
  - [Supported Windows versions](#)
  - [Enabling audio support](#)
  - [RDP vs RemoteApp](#)
  - [Microsoft Windows Server 2016 / 2019 / 2022 Application server](#)
    - [Install Remote Desktop Services](#)
    - [Configuration](#)
      - [Configure deployment service](#)
      - [Configure RemoteApp Collections](#)
      - [Configure RemoteApps](#)
- [Using Windows AD Administrative Center](#)

### Introduction

Although there are many possibilities to integrate the Awingu platform into your existing IT environment, below you can find some useful remarks about this integration effort.

### Using the Active Directory Server as NTP server

When you configure Awingu to use the time service of your Active Directory Server as NTP server, you need to make sure that the AD server has a reliable time source. The easiest option is to sync your AD server with a public NTP server pool, like [nist.gov](https://www.nist.gov).

Example for Microsoft Windows (can only be done using PowerShell):

```
net stop w32time
w32tm /config /syncfromflags:manual /manualpeerlist:"time-a.nist.gov, time-
b.nist.gov, time-c.nist.gov, time-d.nist.gov"
w32tm /config /reliable:yes
net start w32time
```

### Organizational Units for users and application servers

Depending on the needs and the set-up of the customer Windows organization, there are multiple ways of organizing the Awingu platform in the windows domain structure.

If users from separate organizational units (OUs) need to connect to the Awingu platform, we believe it is useful to set-up the application servers into a separated OU. Such a set-up allows to straightforward set-up Group Policy rules on the pool of application servers. If the user processing loopback Group Policy Object (GPO) is set within this application server OU, it is possible to apply and override user side policy rules when they are logging into the application servers. This way special user side policy rules can be applied on the application servers for all users logging in the application servers.

To configure the User Group Policy loopback processing mode, create and link a new GPO to your application server OU where the following is set:

- [Computer Configuration / Policies / Administrative Templates / System / Group Policy / Configure User Group Loopback processing mode:](#)  
This GPO can be set-up in either merge or replace mode.  
In **merge** mode, all user side GPOs of the users original OU are first applied, afterwards the GPOs specific to the application server is applied.



In **replace** mode, only the user side GPO of the application servers are applied. If you opt for replace mode, all the users who start apps on the application server will experience exactly the same behavior.

## Group Policy recommendations

As described above, we recommend adding a few GPOs on the Awingu users and application servers.

## GPOs for the Awingu users







Following GPOs are optional.

Note that in older Windows versions the term "Windows Explorer" is used instead of "File Explorer".

- User Configuration / Policies / Administrative Templates:
  - Start Menu and Taskbar: Remove Run menu from Start Menu: **Enabled**
  - System: Prevent access to the command prompt: **Enabled** (Disable the command prompt script processing also? **No**)
  - System: Ctrl+Alt+Delete Options: Remove Lock Computer **Enabled**
  - System: Ctrl+Alt+Delete Options: Remove Task Manager **Enabled**
  - Windows Components / Desktop Window Manager: Do not allow window animations: **Enabled**
  - Windows Components / File Explorer: Hide these specified drives in My Computer: **Enable** (Pick one of the following combinations: **Restrict all drives**.)
  - Windows Components / File Explorer: Hides the Manage item on the File Explorer context menu: **Enabled**
  - Windows Components / File Explorer: No Computers Near Me in Network Locations: **Enabled**
  - Windows Components / File Explorer: No Entire Network in Network Locations: **Enabled**
  - Windows Components / File Explorer: Prevent access to drives from My Computer: **Enabled** (Pick one of the following combinations: **Restrict all drives**)
  - Windows Components / File Explorer: Remove "Map Network Drive" and "Disconnect Network Drive": **Enabled**
  - Windows Components / File Explorer: Remove File Explorer's default context menu: **Enabled**
  - Windows Components / File Explorer: Remove Hardware tab: **Enabled**
  - Windows Components / File Explorer: Remove Search button from File Explorer: **Enabled**
  - Windows Components / Remote Desktop Services / Remote Desktop Session Host / Session Time Limits: Set time limit for disconnected sessions: **Enabled** (End a disconnected session: **1 minute**)
  - Windows Components / Remote Desktop Services / Remote Desktop Session Host / Session Time Limits: Set time limit for logoff of RemoteApp sessions: **Enabled** (RemoteApp session logoff delay: **Immediately**)
  - Windows Components / Windows PowerShell: Turn on Script Execution: **Enabled** with **Allow only signed scripts**

More settings are described in e.g. <http://nikoscloud.wordpress.com/2013/04/23/how-to-secure-your-remote-desktop-server-with-gpo/>

## GPOs for the application servers

- Computer Configuration / Policies / Administrative Templates / Windows Components / Remote Desktop Services / Remote Desktop Session Host / Connections:
  -  Required: Restrict Remote Desktop Services users to a single Remote Desktop Services sessions: **Disabled**.
  -  Required: Automatic reconnection: **Enabled**.
  -  Needed when you want to publish programs in Awingu as an RDP application: Allow remote start of unlisted programs: **Enabled**.
- Computer Configuration / Policies / Administrative Templates / Windows Components / Remote Desktop Services / Remote Desktop Sessions Host / Session Time Limits:
  -  Required: Set time limit for disconnected sessions: End a disconnected session in **1 minute**
  -  Required: Set time limit for logoff of RemoteApp sessions: RemoteApp session log off delay **Immediately**
- Computer Configuration / Policies / Administrative Templates / Windows Components / Remote Desktop Services / Remote Desktop Sessions Host / Device and Resource Redirection:
  -  Optional: Allow time zone redirection: **Enabled**.

## Set-up Drives connectivity

## CIFS connectivity:

For Awingu to allow connections to the CIFS backend, the specific servers needs to enable SMB shares and SMB connectivity should be allowed to the Awingu environment (for multi node Awingu setup: connect to workers and frontend nodes).

Please be sure the SMB protocol is enabled on your server. You can use following cmdlet:

```
Set-SmbServerConfiguration -EnableSMB2Protocol $true
```

---

## WebDAV drives:

In order to have access to your webdrive, the file structure needs to be published via Webdav on your file servers. Our WebDAV connector needs at least DAV protocol version 2.

To set-up WebDAV via IIS (version 8)

1. Install the IIS server role and features:
  - a. Add the IIS role, no extra feature, ignore WSRM,
  - b. IIS Features: Common HTTP Features: Webdav Publishing, default document, Directory Browsing, Http Errors, Http Redirection, Static Content.
  - c. IIS Features: Health Diagnostics: Custom logging, HTTP logging, Logging Tools
  - d. IIS FeatureS: Authentication: Click on everything
2. Go to Manager IIS Manager
  - a. Add an application pool called webdav
  - b. Rename the Default site
  - c. Add a website: webdav connect it to share location
  - d. Bind it to port 80
  - e. Webdav
    - i. Add Authorizing Rule (that all users can connect)
    - ii. Enable WebDav
  - f. Authentication
    - i. Enable Basic, Digest and Windows.

WebDAV support for large files

By default IIS WebDAV has request filtering turned on, which limits the default upload size to 30000000 Bytes, which is approximately 28.6MiB. Refer to this [guide](#) to change these settings.


In summary

- Open the IIS Manager:
  - Click on the left pane to your WebDAV site.
  - Find and click on the middle pane 'Request Filtering'.
  - Edit on the right pane: 'Edit Request Filtering Settings'
  - In this dialog box, you can change the default value of the Maximum Allowed content length (Bytes).



## Request Filtering

Use this feature to configure filtering rules.



### WebDAV adding MIME Type

If you have MIME types that you want all of your Web sites to recognize, you can add the new MIME types at the global level in IIS. To add a global MIME type

1. In IIS Manager, expand the local computer, right-click the computer/site on which you want to add a MIME type, and click Properties.
2. Click MIME Types.
3. Click Add (or New).
4. In the Extension box, type the file name extension.
5. In the MIME type box, type a valid MIME type.

### WebDAV create default MIME type

1. In IIS Manager, expand the local computer, right-click the computer/site on which you want to add a MIME type, and click Properties.
2. Click MIME Types.
3. Click Add (or New).
4. In the Extension box, type the file name extension.
5. In the MIME type box, type a valid MIME type.
  - a. To create a MIME type for an undefined MIME type, type an asterisk in the Extension box, and type application/octet-stream in the MIME type box.  
Example: File name extension: '\*' MIME type: application/octet-stream
  - b. To create a MIME type for a file without an extension, type a period (.) in the Extension box, and type your MIME type in the MIME type box.  
Example: File name extension: '.' MIME type: application/octet-stream
6. Click OK.



Do not use wildcard MIME-types on production servers. Doing so can result in IIS serving unrecognized files and displaying sensitive information to users. Wildcard MIME-types are intended for testing purposes or in scenarios where Internet Server API (ISAPI) filters have been developed specifically to handle these wildcard scenarios, for example, a custom authentication ISAPI.

## Set-up the Application Servers

### Supported Windows versions

We officially support following Microsoft Windows Application Server versions:

- Microsoft Windows Server 2016
- Microsoft Windows Server 2019
- Microsoft Windows Server 2022

Notes:

- When using certificates on the application servers, the ones Microsoft Windows generates are not compatible with Awingu.

### Enabling audio support

To enable audio in streamed applications, the Windows Audio Service needs to be enabled. To enable this service:

- Open Administrative Tools
- Open Services
- Open Windows Audio service
- Ensure that the service is running

Audio playback works on all supported browsers.

### RDP vs RemoteApp

There are 2 methods to provide applications to Awingu:

- **Remote Application** is an extension to the Remote Desktop Protocol. Remote Application needs to be supported by the application server, and the applications need be exposed over Remote Application. It has several advantages over the regular RDP applications:
  - The window selector (Windows button in the top of the app) is available.
  - The experience on tablets is smoother (especially when rotating the tablet and zooming in/out).
  - The app sharing experience is better.
  - It uses less resources on the application server.
- **RDP application** will make use of the regular Remote Desktop Protocol. **Full desktops** can only be provided via this protocol. When providing an application (no full desktop) to Awingu, the user might notice a delayed closing of the session: after closing the application, a black screen can be shown for up to 3 minutes. This is because Microsoft Windows keeps a print service running. To mitigate this behavior, please follow this solution: <https://support.microsoft.com/en-us/help/2513330/>

### Microsoft Windows Server 2016 / 2019 / 2022 Application server

Please refer to this guide: <http://technet.microsoft.com/en-us/library/hh831447.aspx>

#### Install Remote Desktop Services

1. Log on to Microsoft Windows Server as an Administrator.
2. Open Server Manager. (click Start > Administrative Tools > Server Manager)
3. From Dashboard, click "Add roles and features".
4. Select "Remote Desktop Services Installation", click Next.
5. From deployment type, select "Quick" deployment if you need to quickly deploy all roles to a single server. To have more control, use "Standard Deployment", click Next.
6. From deployment scenario, select "Session-based desktop deployment", click Next.
7. Finish and confirm Installation.
8. Restart the server.

Awingu will detect the Network Level Authentication (NLA) for RDP connection automatically. This setting can be changed in the Server Manager > Remote Desktop Server Settings > Deployment properties > Security settings: Network Level Authentication.

The following message appears when opening a streamed app to that application server: "The server denied the connection". Note that the app will start anyway. To avoid that message, please make sure the Remote Desktop Connection Broker service is running.

#### Configuration

### Configure deployment service

1. Open Server Manager. (click Start > Administrative Tools > Server Manager)
2. Select "Remote Desktop Services".
3. From "Deployment Overview", from the "TASKS" drop-down menu, click "Edit Deployment Properties".
4. From "RD Gateway", select "Automatically ...".
5. From RD Licensing, select "Per User", make sure that the Microsoft Remote Desktop Licensing Server is add to list, or add it.
6. click Apply/OK to finish.

### Configure RemoteApp Collections

1. Open Server Manager. (click Start > Administrative Tools > Server Manager)
2. Select "Remote Desktop Services", select "Collections".
3. If you don't have any collections create new one, the default "QuickSessionCollection"
4. Make sure that Network Level Authentication is not required.
  - a. when on "QuickSessionCollection" on properties click tasks > Edit properties
  - b. Select Security,
  - c. For the Security layer select negotiate.
  - d. Encryption Level: Client Compatible
  - e. Uncheck: Allow connections only from computers running Remote Desktop Service with Network Level Authentication

### Configure RemoteApps

1. Open Server Manager. (click Start > Administrative Tools > Server Manager)
2. Select "Remote Desktop Services", select your collection "RemoteApps" from Collections.
3. From "RemoteApp Programs", from the "Tasks" drop-down menu, click "Publish RemoteApp Programs".
4. From "Publish RemoteApp Programs" form select the apps you want to be available.
5. For application interactivity (ex. edit files) you need to allow command line arguments:  
After publishing, go again to "RemoteApp Programs" section, check the properties of the published app and allow for command line arguments.

**i** On Microsoft Windows 2016/2019/2022 servers, the remoteapp alias cannot be changed through the GUI anymore. However, the remoteapp alias can still be changed via PowerShell. In PowerShell, use the following commands:

```
Import-Module RemoteDesktop
Set-RDRemoteApp -Alias "wordpad" -DisplayName "wordpad_Renamed"
```


### Using Windows AD Administrative Center

In Windows AD Administrative Center, the UPN is not required for a user. However, Awingu does requires this. Please provide a domain UPN as defined here: [https://technet.microsoft.com/en-us/library/cc772007\(v=ws.11\).aspx](https://technet.microsoft.com/en-us/library/cc772007(v=ws.11).aspx)

## Using Awingu on existing Citrix infrastructure

Migrating away from an existing Citrix infrastructure to Awingu is actually a really easy four-step process.

Below is a picture of a typical Citrix XenApp Deployment:



Installing Awingu next to this setup can be achieved by deploying 1 or more (for load distribution or High Availability) Awingu appliances in the Access Layer following this procedure which can be executed in less than 1 hour.


Note: as long Citrix is installed on the resource hosts, you need to have Citrix licenses for the RDP connections from Awingu to the resource hosts.

### Preparation


Download, install and configure Awingu as described in Admin Guide. The Citrix TS Servers (Resource Hosts) are the application servers to configure in [Application Server Management](#).

### Allow non-administrators to RDP to the Citrix servers

When Citrix Virtual Delivery Agent is installed on a machine, non-administrators can no longer RDP to the machine. A new local group called Direct Access Users is created on each Virtual Delivery Agent. Add your non-administrator RDP users to this local group so they can RDP directly to the machine:




Add here the security group for the users which should have access:




**Enable RDP policy in Citrix studio**

To be able to initiate a remote session a policy needs to be added to Citrix. Open the Citrix director and browse to the policy section. On the right top choose Create Policy:



In the search field search for: "Launching of non-published programs during client connection" and select it:



Enable this policy for all objects in this site:



### Edit Setting

**Launching of non-published programs during client connection**

☒ Enabled  
 If a custom client connection specifies an arbitrary program, it will run on farm servers

☐ Disabled  
 Only published applications and published desktops can be run

▼ Applies to the following VDA versions  
 Virtual Delivery Agent: 7.0 Server OS, 7.1 Server OS, 7.5 Server OS, 7.6 Server OS, 7.7 Server OS, 7.8 Server OS, 7.9 Server OS, 7.11 Server OS

▼ Description  
 Specifies whether to launch initial applications or published applications through ICA or RDP on the server. By default, only published applications are allowed to launch.

Give it a meaningful name and enable the policy:

### Create Policy

**Studio**

- ✓ Settings
- ✓ Users and Machines
- Summary**

**Summary**

View a summary of the settings you configured and provide a name for your new policy.

Policy name:  ☒ Enable policy

Description:


Settings configured: 1

Setting	Value
Launching of non-published programs	Enabled (Default: Disabled)


Assigned to: user and machine objects

The settings are applied to all objects in the site.

Set the policy priority higher:




If you want to speed the policy up you can always update them manually:



## Optional: uninstall Citrix software from app servers

The result would be like in the following picture:



Please note that the Netscaler can be optionally used to load balance to the different Awingu appliances but any load balancer will do.

The Citrix Control layer is no longer needed now. The Awingu appliances have all knowledge needed to do the brokerage to the different RDS servers.

## SSL offloader, reverse proxy or loadbalancer settings

### Required Headers

#### WebSocket

WebSocket (WS) technology is based on upgrading a regular HTTP session to a long-living WebSocket connection. To this end, the browser requests a protocol upgrade by sending an HTTP request with the headers for a protocol upgrade. Therefore, the proxy server needs to allow these headers to propagate, to ensure successful HTTP(S) to WS(S) upgrades

Header	Explanation
Connection	This value should be equal to Upgrade
Upgrade	Should be equal to websocket in case of an WebSocket upgrade

The connection header is a [hop-by-hop](#) header, it needs to be explicitly set by the SSL off-loader or proxy stages in between the browser and the Awingu environment. See the Nginx example below, to find the correct example settings.

This header only needs to be set to a limited set of URLs. These requests are only requests of these forms:

- /awingu/RDP
- /awingu/JOIN
- /awingu/API

For a multi-node deployment, please replace awingu with the host names of the RDP Gateways. In general, this can be triggered by the following regular expression: `/.*\/(RDP|API|JOIN)`

#### SSL Offloader Headers

Header	Explanation
X-Forwarded-Proto	This informs Awingu about the originally used protocol.

### Proxy Headers

Setting these headers makes sure that Awingu is aware of the proxy servers in front.

Header	Explanation
X-Real-IP	This should be the IP address of the requesting client
X-Forwarded-For	This should be the IP address of the requesting client
X-Forwarded-Host	This is the FQDN of the server name that was requested by the client
Host	This is the FQDN of the server name that was requested by the client

#### Proxy Timeout

Usually, reverse proxies and SSL offloader have built-in times-outs for their requests to back-end servers. In the case of WebSockets however, a TCP connection is being kept open. Hence, one needs to make sure that the SSL off-loader or reverse proxies are not closing the connection after a few seconds or minutes of inactivity. This would result in streamed applications that are closing automatically for the end-user after this idle timeout value.

Please consult the documentation of your SSL offloader to change these settings in the case of WebSocket. For Nginx based off-loading this setting is as follows:

```
### Proxy Read Timeout:
proxy_read_timeout 3500s;
```

#### Gzip compression

To reduce the size of transmitted data resulting in better performance, Awingu compresses its HTTP(S) traffic using gzip. This is a standard supported by most browsers.

Awingu only compresses the data if the browser supports this, which is indicated by the presence of gzip in the Accept-Encoding header sent by the browser.


Please validate the header **Accept-Encoding** is not stripped by the reverse proxy, as this might result in performance loss.

## Replacing Awingu Nodes

If an Awingu node with the **proxy** service enabled needs to be replaced, and you want to re-use the original IP address, then you need to remove that IP address from the reverse proxy/load balancer before you replace the node with a fresh Awingu appliance. If you don't, that new appliance will redirect port 80 to the 8080, where the installer is running.

After adding the new appliance to Awingu, you can re-add the IP address to the reverse proxy/load balancer.

## Example Nginx Settings

 Due to the SSL 'logjam' vulnerability, you need to generate a new Diffie-Hellman group for TLS. For more information, please see <https://weakdh.org/sysadmin.html>.

In order to generate a new Diffie-Hellman group, please use the following command:

```
openssl dhparam -out dhparams.pem 2048
```

After you have generated the new Diffie-Hellman group, you need to reference it in your Nginx configuration with the `ssl_dhparam` variable (see below).

The following config settings are working Nginx for SSL off-loading:

```
upstream frontends {
    server <IP-OF-AWINGU-VM>:80;
}

server {
    listen            80;
    server_name       sgo.yourcompany.com;
    ## redirect http to https ##
    rewrite           ^ https://$server_name$request_uri? permanent;
}

server {
    listen            443;
    ssl               on;
    server_name       sgo.yourcompany.com;
    ssl_certificate    sslcerts/yourcompany.com.chained.crt;
    ssl_certificate_key sslcerts/yourcompany.com.key;
    # due to the SSL 'Poodle' vulnerability, SSLv3 should be disabled
    ssl_protocols     TLSv1.2 TLSv1.3;
    ssl_ecdh_curve     X25519:P-256:P-384:P-224:P-521;
    ssl_ciphers        EECDH+AESGCM:EDH+AESGCM;
    ssl_prefer_server_ciphers on;
    ssl_dhparam        /etc/ssl/private/dhparams.pem;

    keepalive_timeout 60;
    ssl_session_cache  shared:SSL:10m;
    ssl_session_timeout 10m;

    # Gzip Settings
    gzip on;
    gzip_disable "msie6";
    gzip_types
        application/atom+xml
        application/javascript
        application/x-javascript
        application/json
```

```

application/ld+json
application/manifest+json
application/rss+xml
application/vnd.geo+json
application/vnd.ms-fontobject
application/x-font-ttf
application/x-web-app-manifest+json
application/xhtml+xml
application/xml
font/opentype
image/bmp
image/svg+xml
image/x-icon
text/cache-manifest
text/css
text/plain
text/vcard
text/vnd.rim.location.xloc
text/vtt
text/x-component
text/x-cross-domain-policy;

### We want full access to SSL via backend ###
location / {
    proxy_pass http://frontends;

    ### force timeouts if one of backend is died ##
    proxy_next_upstream error timeout invalid_header http_500 http_502 http_503 http_504;

    ### Set headers ####
    proxy_set_header    Accept-Encoding    "";
    proxy_set_header    Host                $host;
    proxy_set_header    X-Real-IP          $remote_addr;
    proxy_set_header    X-Forwarded-Host   $host;
    proxy_set_header    X-Forwarded-Server $host;
    proxy_set_header    X-Forwarded-For    $proxy_add_x_forwarded_for;

    ### Most PHP, Python, Rails, Java App can use this header ###
    proxy_set_header    X-Forwarded-Proto $scheme;

    ### By default we don't want to redirect it ####
    proxy_redirect      off;

    location ~ /\.*/(RDP|API|JOIN|RAH) {
        proxy_pass http://frontends;

        # WebSocket support (nginx 1.4)
        proxy_http_version 1.1;
        proxy_set_header Upgrade $http_upgrade;
        proxy_set_header Connection "upgrade";
        proxy_set_header    Accept-Encoding    "";
        proxy_set_header    Host                $host;
        proxy_set_header    X-Real-IP          $remote_addr;
        proxy_set_header    X-Forwarded-Host   $host;
        proxy_set_header    X-Forwarded-Server $host;
        proxy_set_header    X-Forwarded-For    $proxy_add_x_forwarded_for;
        ### Proxy Read Timeout: 12h
        proxy_read_timeout 43200s;
    }

    location /upload/ {
        client_max_body_size 0;

        proxy_pass http://frontends/$request_uri;
        proxy_request_buffering off;
        proxy_buffering off;
    }
}

```

```

        proxy_cache off;
        proxy_set_header Host $host;
        proxy_set_header X-Forwarded-For $proxy_add_x_forwarded_for;
        proxy_set_header X-Forwarded-Proto $scheme;
    }
}

```

We recommend using **minimum 512 worker connections per 50 concurrent users**. This can be configured in `/etc/nginx/nginx.conf`. For the number of open files, take some additional margin. Example for **200 users**:

```

worker_rlimit_nofile 3000;

events {
    worker_connections 2048;
}

```

## Multi Factor Authentication



## Using Awingu built-in OTP

- [Introduction](#)
- [Configuration](#)
- [User Set-Up](#)

### Introduction

Awingu has two built-in Multi-Factor Authentication (MFA) options: counter based or time based OTP (one time password).

Note that the OTP token will also be asked when required to login when using Awingu as Identity Provider or as Reverse Proxy.

### Configuration

OTP can be enabled for each domain, see [User Connector Configuration](#) for all available settings and detailed information.

### User Set-Up

The first time a user wants to login after MFA is enabled, they need to do following steps only once:

1. Download an authenticator app (typically on their smartphone) supporting the chosen MFA authentication method.
2. After providing credentials on the Awingu login page, the user will be forwarded to a page showing a QR code and a secret.
3. The user scans the QR code with their phone (or enters the secret manually).
4. The first token is generated in the app. The user enters that token to proceed.

Next time the user logs in, they will only need to provide their regular credentials and their token.

They will not need to scan the QR code again, unless the token has been reset.

Any authenticator app that supports counter-based authentication (also called HOTP) or time-based authentication (also called TOTP) should work with Awingu's two-factor authentication.

Some suggestions:

**Android:** Authy, Google Authenticator, Microsoft Authenticator, Sophos Authenticator, ...

**iOS:** Authy, Google Authenticator, Microsoft Authenticator, Sophos Authenticator, ...

**Linux:** Authy

**Windows Phone:** Microsoft Authenticator

**Windows:** Authy (requires one-time phone verification, can be done by SMS)

Most authenticators require a phone number in some way. If the user does not have a mobile device available to them for doing MFA, they could also use a browser extension such as [Authenticator.cc](#). When setting up MFA with this extension, you can either use its Scan QR feature or you can use the text code on the Awingu MFA set-up screen (upon login).

Note that it's worth evaluating different authenticator apps as there may be specific limitations or advantages.

Some useful criteria for such an exercise are:

- back-up
- synchronization
- multi platform / operating system
- device type (smartphone, tablet, pc, ...)
- does it require linking a phone number
- support for HOTP and/or TOTP

## Integrating Awingu with DUO

- [Introduction](#)
- [Prerequisites](#)
- [Configuring your Awingu application in Duo](#)
- [Configuring Duo in Awingu](#)
- [Users](#)
- [Known Limitations](#)

### Introduction

Awingu integrates with Duo for multi-factor authentication.

This guide will walk you through the different steps required to configure both Awingu and Duo to enable the integration.


### Prerequisites

This guide assumes you have administrative access to a working Awingu environment and an active Duo account. The Duo personal plan is sufficient to evaluate Duo integration with Awingu.


As Duo is a SaaS service, the Awingu environment requires access to the Duo SaaS service. This is `TCP 443` to the API hostname of your configured application (`<your_api>.duosecurity.com`).

### Configuring your Awingu application in Duo


Sign-in to your Duo account and select **Applications** in the menu.



To add your Awingu application, click *Protect an Application* and select *Auth API* as type.



This will result in a pre-configured application in Duo. The *Details* section of the application provides you with all details required to configure Awingu later on.



Before moving over to configure Awingu, we need to change some default values of the Duo settings in the *General* section.

**Settings**

**General**

Type: Auth API

Name: Awingu Doc  
Duo Push users will see this when approving transactions.

Username normalization: ☐ None ☒ **Simple**  
"DOMAIN\username", "username@example.com", and "username" are treated as the same user.  
Controls if usernames should be altered before trying to match them to a user account.

Voice greeting: Welcome to Duo.  
Specify the message read to users who use phone callback, followed by authentication instructions.

Notes:  
For internal use.

Permitted groups: ☒ Only allow authentication from users in certain groups  
Select groups  
When unchecked, all users can authenticate to this application.

[Save Changes](#)

Please make sure the *simple* username normalization is enabled, or all authentication requests will fail. In this section you can also provide a more meaningful name for your Duo Awingu application.

Save your changes and your Duo application is Awingu ready.

## Configuring Duo in Awingu

To configure MFA in Awingu, navigate to *Configure > User Connector* for your domain. Please be aware that the MFA configuration is domain specific.

Scroll down to the *Multi-factor Authentication* section and select the *Duo Security* mode.

The screenshot shows the 'Multi-factor Authentication' section of the Awingu System Management Console. The 'Mode' is set to 'Duo Security'. The 'API Hostname' is 'api-eb0919f5.duosecurity.com', the 'Integration Key' is 'DINRO9QR7Q6RRHN0P4W2', and the 'Secret Key' is masked with '\*\*\*\*\*'. Below this is the 'SSO Identity Provider (IdP)' section, where the 'State' is 'Disabled', and the 'Issuer', 'Logout URL', 'Certificate', and 'Private Key' fields are all empty. At the bottom, there is an 'SSO Services' section with a table header showing 'Name' and 'State'.

Name	State

System Management Console - © 2012-2016 Awingu N.V. - Eula 3.3

Enter the beforementioned corresponding values from the Duo portal and press apply.

Now Awingu is configured to use *Duo* as MFA provider for all users of the selected domain!

## Users

To enable *Duo* MFA for your users, the users should be enrolled at *Duo*. They can be enrolled manually, imported or synced with Active Directory.

Please have a look at Duo's *Enrolling Users* documentation ([https://duo.com/docs/enrolling\\_users](https://duo.com/docs/enrolling_users)) to see what option fits best your use case.

## Known Limitations

- Awingu **does not support users with status bypass**  
Duo provides a feature that allows you to configure users to skip MFA. This can be done by setting the user's status to *bypass*. Awingu does not honour this status and thus will prevent the user to sign in.


## Awingu Single Sign On (SSO)

Next to the standard username/password login, Awingu is also able to do a full Single Sign-on (SSO) via an external Identity Provider.

How does it work?

### Standard Login

In the *standard setup* Awingu validates directly against the Active Directory (AD) if the username/password provided on the Awingu login page is correct. It makes a connection over LDAP(s) and if the credentials are valid, it will fetch the security groups over LDAP(s) of the user and build up the Awingu user profile and landing page. When starting a virtual desktop (VDI) or a remote application (remote app) the credentials are transparently injected into the RDP stream and the VDI or remote app is started.



### SSO Login

When switching to SSO, the login becomes a 2 step process.

Firstly Awingu no longer does the authentication of the user itself, but this is handled by an external Identity Provider (IDP). As the external IDP doesn't expose the passwords and the Microsoft Remote Desktop Protocol (RDP) doesn't support ticket/token based logins, in a second step, the credential based login towards back-end systems (remote app, VDI, storage, ...) is replaced by a certificate based login mechanism.



### Configuration

To setup Single Sign-On several steps need to be completed.

1. [Enable pre-Authentication](#)
  - a. Add Awingu as a trusted application into your IDP

- i. [Azure AD](#)
    - ii. [Microsoft ADFS](#)
    - iii. [Google ID](#)
  - b. Configure Awingu for SAML or OpenID connect authentication
  - c. Test & Troubleshoot pre-authentication
2. [Enable Single Sign-On](#)
- a. Generate Certificate & Setup the intermediate Sub-CA
  - b. Validate if Windows backend is correctly configured for Awingu SSO
  - c. Configure Awingu for SSO

**i** Pre-authentication against an external IDP is possible for SAML (v2) and OpenID Connect based IDPs.

In general Awingu should be compatible with any IDP that supports these standards. In this manual we describe how to do the setup for following tested IDPs:

- Azure AD (via SAML)
- ADFS (via SAML)
- Google (via OpenID Connect)

### End User Flow:

- When a user accesses the Awingu landing page, Awingu will check if the user has a valid authentication token with the configured IDP.
- If this is not the case yet, Awingu will redirect the browser to the IDP. The user will need to authenticate first against the IDP. If successful, the IDP will redirect the User to the Awingu landing page.
- Awingu will ask the user for their Windows password.
- User will be logged in to the Awingu Workspace
- From the Workspace they can start Apps, Desktops and get access to the Drives.

From a technical point of view Awingu needs a valid SAML or OpenID Connect ticket before it allows the user to login to the Awingu portal. As the Microsoft RDP protocol doesn't support SAML or any other ticket based login mechanisms and as the IDP doesn't expose or include the entered password inside the ticket, the user needs to enter his Windows password (again) before he can login to the Awingu portal. The login into the portal and the apps happens via the standard credential based authentication mechanism.

To get the extra "Windows password" removed you need to [upgrade from pre-auth to SSO](#).

### Use Cases:

By enabling this pre-authentication you can enable some extra use cases:

#### Conditional Access

Awingu allows access from any device. For some organizations this is not desired and they want to limit access to only managed devices. Via a firewall or reverse proxy in front of Awingu you can already do some first filtering (for example only allow connections from a specific range of IP addresses) but thanks to the pre-authentication you can use the conditional access features of your IDP to, for example, limit access to Awingu so login can only be done on managed devices.

See <https://docs.microsoft.com/en-us/azure/active-directory/conditional-access/require-managed-devices> on how to do this when using Awingu in combination with Azure AD.

### Add Awingu as a trusted application into your IDP

Awingu can work with any external IDP that supports SAML or OpenID Connect. Please check the documentation of your IDP on how to add a trusted application.

Azure AD, Azure AD with OPSWAT, Microsoft ADFS & Google have been tested in combination with Awingu.

Please check following documentation on how to configure them:

- [Setting up Azure AD as an external IDP for Awingu](#)
- [Setting up Azure AD with OPSWAT as external IDPs for Awingu](#)
- [Setting up Microsoft ADFS as an external IDP for Awingu](#)
- [Setting up Google as an external IDP for Awingu](#)

### Configure Pre-Authentication

Before you start configuring the pre-authentication make sure there is a host header set on the tenant. Go to **Global - Domains** - Select your domain. Make sure the public DNS name of the Awingu environment is set in the list of host headers for this domain. So for example if your public url for your Awingu environment is <https://awingu.company.com>, then make sure that in the list of host headers "awingu.company.com" is set.



To start the configuration itself of the pre-authentication, login to Awingu as an admin and open the system settings: Go to **Configure - User Connector - Federated Authentication** .

Set:

- Type to "Pre-Authentication"
- Select the correct protocol: SAML, SAML with Intermediate IdP or OpenID
- Provide the URL pointing to your Awingu environment. This URL will be used to construct the return URL you will need in the configuration of the IDP. (for example <https://awingu.company.com/>)

### Federated Authentication

Type

Pre-Authentication

Protocol

Required

Workspace URL

The Workspace base URL used to construct the redirect URL (for OpenID) or the ACS URL (for SAML) for the Authentication Provider.

Required

Cancel

Apply

Configure Pre-Authentication with SAML

To use SAML for an external IDP the following fields need to be provided:

- **Entity Id:** The unique identifier on your IDP for the Awingu application.
  - For Azure AD this is "**spn:**<application-id>" (example spn:1234-5678-90xxxx). The Application ID is a property of the Azure Application (see [Setting Up Azure AD as an external IDP for Awingu](#))
  - For ADFS this is the relying party identifier configured when setting up your relying party trust in ADFS (see [Setting Up ADFS as an external IDP for Awingu](#))
- **Metadata Type:** How is the SAML Federation Metadata provided? Depending on the capabilities of the used Identity Provider.
  - URL: The appliance should download the metadata at every login attempt using a provided URL.
  - XML: The metadata is uploaded as a static .XML file.
- **Metadata URL:** The URL of the federation metadata document. When using https please make sure the URL is accessible via a public trusted certificate. If your certificate is not publicly trusted, then you can host the metadata.xml file on another web server as a workaround.
- **Metadata XML:** The .xml file providing the federation metadata to upload to the appliance.
- **Single Logout:** Enable this option to make sure the user will also be logged out of the the IdP if he logs out of this workspace. Mind that this only works if the logout is initiated in the front end by the user. Requires configuration on the Identity Provider. See the documentation: [Setting up Azure AD as an external IDP for Awingu](#)
- **Username Claim URL:** The SAML response received by Awingu contains different properties (e.g. email, UPN, sAMAccountName, display name,...). Using the Username Claim URL you can specify which property will be used when logging into Awingu. When Single Sign-On (SSO) is enabled, the Username Claim URL needs to be set to the UPN.
  - When using Azure AD the default value is used ( <http://schemas.xmlsoap.org/ws/2005/05/identity/claims/name> ).
  - When using ADFS it is best to directly use the UPN ( <http://schemas.xmlsoap.org/ws/2005/05/identity/claims/upn> ).
- **Display Name Claim URL** will be used on the login page of Awingu when the user successfully logged into the identity provider (e.g. "Welcome David"). The default value will be the claim URL to the given name ( <http://schemas.xmlsoap.org/ws/2005/05/identity/claims/givenname> ) property. Possible other claims URIs can be found here: <https://docs.microsoft.com/en-us/windows-server/identity/ad-fs/technical-reference/the-role-of-claims>
- **Workspace URL:** the public DNS name for the Awingu work space

**Entity Id**   
 Unique identifier of the SAML IDP  
 Required

**Metadata Type** ☒ URL  
☐ XML  
 The type of metadata configured

**Metadata URL**   
 The metadata URL eg.: "https://login.microsoftonline.com/<tenant-id>/federationmetadata/2007-05/federationmetadata.xml".  
 Required

**Single Logout** ☐ Enabled  
☒ Disabled  
 Also logs the user out of the IdP if he logs out of this workspace. The Workspace Single Logout URL will need to be configured on the IdP side.


**Workspace Single Logout URL**   
 The URL that will be redirected to after the IdP finishes the Single Logout process. This needs to be configured on the IdP side.

**Username Claim**   
 The SAML claim of the username e.g. http://schemas.xmlsoap.org/ws/2005/05/identity/claims/name. When Single-Sign-On (SSO) is enabled, the Username Claim needs to refer to the UPN.

**Display Name Claim**   
 The SAML claim of the display name e.g. http://schemas.xmlsoap.org/ws/2005/05/identity/claims/givenname

**Workspace URL**   
 The Workspace base URL used to construct the redirect URL (for OpenID) or the ACS URL (for SAML) for the Authentication Provider.

#### Configure Pre-Authentication with SAML and Intermediate IdP



SAML Login flow when using an intermediate IdP:

- When a user accesses the Awingu landing page, the user will be redirected to the Primary IDP.
- After the user logs in to the Primary IDP, he will be redirected to the Intermediate IDP (Intermediate ACS URL).
- The Intermediate IDP can perform additional checks (device compliance, monitoring, credentials,...).
- When the Intermediate IDP allows the user through, it will redirect him to Awingu (ACS URL).
- Awingu then determines if the user is successfully pre-authenticated by validating the SAML response from the Intermediate IDP (using the Intermediate Signing Certificate).

To use SAML with an intermediate IDP the following extra fields need to be provided:

- **Intermediate ACS URL:** The Primary IDP redirects to this URL in case of successful authentication.
- **Intermediate Signing Certificate:** Awingu uses this certificate to check the SAML response from the Intermediate IDP.

See [Setting up Azure AD with OPSWAT as external IDPs for Awingu](#) for an example configuration where Azure AD is used as the Primary IDP and OPSWAT as the Intermediate IDP.

#### Configure Pre-Authentication with OpenID

To use OpenID for an external IDP the following fields need to be provided:

- **Discover URL:** The OpenID Connect discovery URL.
  - For google this is: <https://accounts.google.com/.well-known/openid-configuration> (See <https://developers.google.com/identity/protocols/OpenIDConnect> for more details)
- **Client ID:** OpenID connect client ID
- **Client secret:** *Optional.* For Google & Azure this is not needed and can be left blank
- **IdP Logout URL:** *Optional.* When an URL is provided to logout the user from the IdP, Awingu will redirect to it after the user logs out of Awingu. E.g. when using Google as IdP this could be <https://www.google.com/accounts/Logout>.
- **Username key:** Key in the Open id\_token which holds the Awingu username.
  - For Google use email
  - For Azure use upn
- **Display name key:** Key in the Open id\_token which holds the display name
  - For Google use email
  - For Azure use name

Discovery URL	<input type="text"/>
	The OpenID Connect discovery URL eg. <a href="https://login.microsoftonline.com/&lt;tenant-id&gt;/well-known/openid-configuration?appid=&lt;application-id&gt;">https://login.microsoftonline.com/&lt;tenant-id&gt;/well-known/openid-configuration?appid=&lt;application-id&gt;</a> <b>Required</b>
Client ID	<input type="text"/>
	OpenID Connect client id. For Azure this would be the application id. <b>Required</b>
Client secret	<input type="text"/>
	Optional. Not needed for Azure or Google.
Username key	<input type="text" value="upn"/>
	Key in the Openid id_token which holds the Awingu username. This would usually be the UPN.
Display name key	<input type="text" value="name"/>
	Key in the Openid id_token which holds the display name.

## Testing & troubleshooting pre-authentication

**i** When testing pre-authentication for the first time, please make sure you use a private or incognito browser window. In some cases there might still be active cookies in your main browser window that prevent the correct login.

If pre-authentication works via incognito windows but not via your normal browser window, then delete your browser cookies from today.

If the configuration is done correctly both on the IDP as well as in the Awingu configuration you should experience the correct end user flow as described above.

In the event of an issue, this chapter will help you in troubleshooting. We have documented the most common issues.

#### How to access the system settings when pre-auth has a faulty configuration?

Once pre-authentication is enabled, all Windows based accounts will need to first authenticate against the IDP before they can login to Awingu. In the event of an issue with the IDP configuration or Awingu configuration, the following procedures can be used to access the Awingu system settings. All these procedures **assume that you execute them in a private/incognito browser window** and will only work for **the built-in Awingu admin user**.

1. Access the Awingu appliance on a different URL than the one that is linked to your IDP:

- a. In case of a multi-tenant setup login to another tenant where no pre-auth is configured. In this case the tenant must also be administrative to allow modification to the impacted tenant. This procedure will also work with all admin users on the other tenant.
  - b. In case of a single tenant or multi-tenant without other administrative domains add a new/other DNS record for the system or try to connect with the IP rather than the DNS name. In this case there might be certificate issues or the extra DNS names may not exist on a reverse proxy in front of Awingu.
2. Access the Awingu appliance via the "noPreAuth" flag: Assuming your Awingu URL is <https://awingu.company.com> - by going to <https://awingu.company.com/login?noPreAuth> (**case sensitive!**) you will get the login prompt with username / password. As previously mentioned this login will only work with the built-in Awingu admin user.

Awingu doesn't do a redirect to my IDP

When a user goes to Awingu the redirect to the IDP is not working. Instead of being redirected to the IDP the user gets a login/password prompt and when typing in their username / password an error is shown stating that pre-authentication is required.

This issue mostly happens when either

1. There is no (or faulty) host header set in the domain settings of Awingu for this tenant. (**System Settings - Global - Domains**).
2. Awingu can't access/read the metadata URL.

To fix please check:

- If network connectivity from the Awingu appliance to the Metadata URL is working. Check via the troubleshoot tools if DNS and network ports are open. If needed configure Awingu to use a proxy server (see **System Settings - Global - Connectivity - HTTP Proxy**) to access a public Metadata URL. If no access is possible to the metadata url you can also upload the XML file directly on the Awingu appliance.
- If the metadata URL is hosted on an internal website and the connection is done over https make sure the certificate is a public certificate, not a private certificate that is only known in the windows environment. If needed you can also move the XML file from the internal website to the Awingu appliance by uploading the file.
- In the domains settings of this tenant the correct public host header for the Awingu appliance is set.

Awingu shows an InvalidNameIDPolicy

This error mostly occurs when using Awingu in combination with ADFS.

User goes to Awingu, Awingu redirects to the ADFS authentication page, authentication into ADFS is successful but when returning to Awingu you get the following error:

```
{ "error": "The status code of the Response was not Success, was Requester -> urn:oasis:names:tc:SAML:2.0:status:InvalidNameIDPolicy" }
```

The error could mean one of the following:

- NameID claim is missing
- NameID claim is in the wrong format. The format must be "emailaddress"
- NameID claim is empty

Please check that the transform claim is correctly configured on the ADFS side:

**Add Transform Claim Rule Wizard**

### Configure Rule

**Steps**

- Choose Rule Type
- Configure Claim Rule

You can configure this rule to map an incoming claim type to an outgoing claim type. As an option, you can also map an incoming claim value to an outgoing claim value. Specify the incoming claim type to map to the outgoing claim type and whether the claim value should be mapped to a new claim value.

Claim rule name:

Rule template: Transform an Incoming Claim

Incoming claim type:

Incoming name ID format:

Outgoing claim type:

Outgoing name ID format:

☒ Pass through all claim values  
☐ Replace an incoming claim value with a different outgoing claim value  
     Incoming claim value:   
     Outgoing claim value:    
☐ Replace incoming e-mail suffix claims with a new e-mail suffix  
     New e-mail suffix:   
     Example: fabrikam.com

< Previous    **Finish**    Cancel

Please also check that the accounts you are using have a valid UPN specified:

**win-admin Properties**

Organization	Member Of	Dial-in	Environment	Sessions
Remote control	Remote Desktop Services Profile			COM+
General	Address	Account	Profile	Telephones
			Delegation	

**User login name:**

**User login name (pre-Windows 2000):**

☐ Unlock account

**Account options:**


☐ User must change password at next logon  
☐ User cannot change password

## Setting up Azure AD as an external IDP for Awingu

SAML pre-authentication can be configured with Azure AD as the identity provider. The following instructions will show how to configure this in Awingu and in Azure AD.

### Register a new Azure Application

1. Login to the Azure Portal
2. Navigate to Azure Active Directory
3. Select from the side bar: *App registrations*
4. Select: *New Registration*
5. Provide a name and supported account type
6. Add redirect URI:
  - a. Set the type to Web
  - b. Provide the following URL: <https://awingu.company.com/api/saml/> where "[awingu.company.com](https://awingu.company.com/)" points to your Awingu Environment. (Make sure to add the trailing slash)



Collect the needed information to complete the setup on the Awingu appliance

There are two properties that we will need from the Azure Application during the configuration in Awingu:


- Application ID (format: xxxxxxxx-xxxx-xxxx-xxxx-xxxxxxxxxxxx) which can be found in the properties of the Azure Application on the Overview page of the app.
- Federation metadata document URL (format: <https://login.microsoftonline.com/xxxxxxxx-xxxx-xxxx-xxxx-xxxxxxxxxxxx/federationmetadata/20-07-06/federationmetadata.xml>) which can be found on the dialog that appears when clicking Endpoints on the Overview page of the app.

### Configuration for Single Logout

During the configuration of the IdP in the Federated Authentication section of Awingu, the Single Logout feature(SLO) can be enabled. When enabled, the user will also be logged out of the IdP when logging out of Awingu.

The following configuration is required on the IdP:

1. Open the previously created Application in the Azure Portal
2. Click *Authentication* in the left menu
3. Add the Workspace Single Logout URL (shown in the Federated Authentication configuration in Awingu) to the *Front-channel logout URL*



Note: Only front-channel logout is supported. If the users closes his browser during the logout process, the user might still be logged in to the IdP.

## Setting up Azure AD with OPSWAT as external IDPs for Awingu

SAML pre-authentication can be configured with Azure AD as the Primary IDP and OPSWAT as the Intermediate IDP. The following instructions demonstrate how to configure this in Awingu, in Azure AD and OPSWAT.

### Register a new Azure Enterprise Application

1. Login to the Azure Portal
2. Navigate to Azure Active Directory
3. Select from the side bar: *Enterprise applications*
4. Click *Add* and *Create your own application*
5. Provide a name and choose *Integrate any other application you don't find in the gallery (Non-gallery)*
6. Collect the needed information by clicking on *Single sign-on* in the left menu and *SAML* as the single sign-on method.
  - a. Copy the App Federation Metadata URL(1).
  - b. Download the SAML Signing Certificate (Base64)(2).
  - c. Copy the Login URL(3).

### Configure OPSWAT

1. Login to the OPSWAT MetaAccess console
2. Add Identity Provider:
  - a. Navigate to *Secure Access > Access Methods*.
  - b. Click the *Identity Providers* tab.
  - c. Click the *Create New Identity Provider* button.
  - d. Provide a name and upload the previously downloaded SAML Signing Certificate (Base64)(2) from the Azure Enterprise Application.
3. Add Protected App:
  - a. Navigate to *Secure Access > Protected Apps*.
  - b. Click the *Add Protected Application* button
  - c. Select *IdP Method*.
  - d. Select the previously created IDP (Choose from existing IDPs).
  - e. Fill in the form:
    - i. Choose an Application Name.
    - ii. Define an Access Mode:
      1. Monitor: Audit logs will be created, access will not be restricted.
      2. Enforced: You will only be able to login if you install the OPSWAT MetaAccess client. You will get a link to download this if you try to login without it being installed.
    - iii. IdP Login URL: Provide the previously copied Login URL(3) from the Azure Enterprise Application.
    - iv. App ACS URL:
      1. Login to Awingu and Open the System Settings
      2. Navigate to the *Configure > User Connector > Federated Authentication* section
      3. Select *Pre-authentication* or *Single sign-on* as Type (See [Enabling Single Sign-On \(SSO\)](#) for the additional configuration steps to enable Single sign-on).
      4. Select *SAML with Intermediate IdP* as the protocol.
      5. Copy the read-only field *ACS URL* and use this as the App ACS URL in the Protected App form.
    - v. Click *Add*
  - f. Collect the needed information by opening the newly created Protected App and clicking the *SSO Setup Instructions* tab.
    - i. Copy the ACS URL(4).
    - ii. Download the Certificate(5).

### Update the Azure Enterprise Application

1. Login to the Azure Portal, navigate to the Enterprise Applications and open the recently created Enterprise Application.
2. Click *Single sign-on* in the left menu
3. Click the *Edit* button of the first section (*Basic SAML Configuration*)
  - a. Specify an Entity ID(6) and copy this value.
  - b. Add the copied ACS URL from OPSWAT as a Reply URL(4).

### Enable Pre-authentication with Intermediate IdP in Awingu

1. Login to Awingu and open the System Settings
2. Navigate to the *Configure > User Connector > Federated Authentication* section
  - a. **Entity Id:** Add the copied Entity ID(6) from the step before.
  - b. **Metadata Type:** URL
  - c. **Metadata URL:** The previously copied Metadata URL (1).
  - d. **Intermediate ACS URL:** The previously copied ACS URL from OPSWAT (4)
  - e. **Intermediate Signing Certificate:** The previously downloaded certificate from OPSWAT(5).
3. See [enabling pre-authentication](#) for the general configuration.

## Setting up ADFS as an external IDP for Awingu


To configure Awingu with ADFS as the external IDP, you first need to add Awingu as a "Relying Party Trust" in ADFS, after this we need to setup the correct claims to be passed to Awingu.

Before you start make sure that you know your Awingu Base URL.

Add Awingu as a relying party trust:


Go to your ADFS host and start the "AD FS Management Tool", select Relaying Party Trusts and right click on it, then open the "Add Relaying Party Trust ..." wizard

On the welcome screen select "claims aware" and click on start



On the Select Data Source page select "Enter data about the relying party manually"





**Add Relying Party Trust Wizard**

**Select Data Source**

**Steps**

- Welcome
- Select Data Source
- Specify Display Name
- Configure Certificate
- Configure URL
- Configure Identifiers
- Choose Access Control Policy
- Ready to Add Trust
- Finish

Select an option that this wizard will use to obtain data about this relying party:

☐ Import data about the relying party published online or on a local network

Use this option to import the necessary data and certificates from a relying party organization that publishes its federation metadata online or on a local network.

Federation metadata address (host name or URL):

Example: fs.contoso.com or https://www.contoso.com/app

☐ Import data about the relying party from a file

Use this option to import the necessary data and certificates from a relying party organization that has exported its federation metadata to a file. Ensure that this file is from a trusted source. This wizard will not validate the source of the file.

Federation metadata file location:


Browse...

☒ Enter data about the relying party manually

Use this option to manually input the necessary data about this relying party organization.

< Previous   Next >   Cancel

Select a Display Name. This will be the name that is displayed in the overview of all relying party trusts.



**Add Relying Party Trust Wizard**

**Specify Display Name**

**Steps**

- Welcome
- Select Data Source
- Specify Display Name
- Configure Certificate
- Configure URL
- Configure Identifiers
- Choose Access Control Policy
- Ready to Add Trust
- Finish

Enter the display name and any optional notes for this relying party.

Display name:

Awingu

Notes:

< Previous   Next >   Cancel

Awingu doesn't need an extra certificate to encrypt the claims. Leave this blank

**Add Relying Party Trust Wizard**

**Configure Certificate**

**Steps**

- Welcome
- Select Data Source
- Specify Display Name
- Configure Certificate**
- Configure URL
- Configure Identifiers
- Choose Access Control Policy
- Ready to Add Trust
- Finish

Specify an optional token encryption certificate. The token encryption certificate is used to encrypt the claims that are sent to this relying party. The relying party will use the private key of this certificate to decrypt the claims that are sent to it. To specify the certificate, click Browse.

Issuer:  
Subject:  
Effective date:  
Expiration date:

View... Browse... Remove

< Previous Next > Cancel

Select the SAML 2.0 WebSSO protocol and set the URL to your Awingu SAML URL. The URL can be found in the pre-authentication configuration in Awingu System Settings, but is typically your Awingu base URL + /api/saml. So for example <https://awingu.company.com/api/saml>

**Add Relying Party Trust Wizard**

**Configure URL**

**Steps**

- Welcome
- Select Data Source
- Specify Display Name
- Configure Certificate
- Configure URL**
- Configure Identifiers
- Choose Access Control Policy
- Ready to Add Trust
- Finish

AD FS supports the WS-Trust, WS-Federation and SAML 2.0 WebSSO protocols for relying parties. If WS-Federation, SAML, or both are used by the relying party, select the check boxes for them and specify the URLs to use. Support for the WS-Trust protocol is always enabled for a relying party.

☐ Enable support for the WS-Federation Passive protocol

The WS-Federation Passive protocol URL supports Web-browser-based claims providers using the WS-Federation Passive protocol.

Relying party WS-Federation Passive protocol URL:

Example: <https://fs.contoso.com/adfs/ls/>

☒ Enable support for the SAML 2.0 WebSSO protocol

The SAML 2.0 single-sign-on (SSO) service URL supports Web-browser-based claims providers using the SAML 2.0 WebSSO protocol.


Relying party SAML 2.0 SSO service URL:

<https://awingu.daas.com/api/saml>


Example: <https://www.contoso.com/adfs/ls/>

< Previous Next > Cancel

This field should correspond to the "identity ID" specified in the Awingu pre-authentication configuration.



The rest of the configuration can be done with default settings, no changes needed:



Add the necessary Awingu claims

Once the "Trusted Relying Party" is created you can add claims by selecting the relying party trust and then in the actions menu choose the "Edit Claim Issuance Policy ..."

*First - We will select the AD attributes that will be sent as claims to Awingu.*

Add a rule based on the "Send LDAP Attributes as Claims" template:

Set the Attribute store to: Active Directory

Add 2 Claims:

- User-Principal Name UPN
- Display-Name Given Name

In this case User-Principal Name and Display-Name will be sent to Awingu.

**Add Transform Claim Rule Wizard**

### Configure Rule

**Steps**

- Choose Rule Type
- Configure Claim Rule

You can configure this rule to send the values of LDAP attributes as claims. Select an attribute store from which to extract LDAP attributes. Specify how the attributes will map to the outgoing claim types that will be issued from the rule.

Claim rule name:

Rule template: Send LDAP Attributes as Claims

Attribute store:

Mapping of LDAP attributes to outgoing claim types:

LDAP Attribute (Select or type to add more)	Outgoing Claim Type (Select or type to add more)
User-Principal-Name	UPN
Display-Name	Given Name
*	

< Previous Finish Cancel

Second - We will add the mandatory Name ID claim.

Add a rule based on the "Transform an Incoming Claim" template:

As the name ID field is a mandatory field in the ADFS setup and the format must be Email, we need to add a transform rule that sets the Name ID field based on the existing UPN.

**Add Transform Claim Rule Wizard**

### Configure Rule

**Steps**

- Choose Rule Type
- Configure Claim Rule

You can configure this rule to map an incoming claim type to an outgoing claim type. As an option, you can also map an incoming claim value to an outgoing claim value. Specify the incoming claim type to map to the outgoing claim type and whether the claim value should be mapped to a new claim value.

Claim rule name:

Rule template: Transform an Incoming Claim

Incoming claim type:

Incoming name ID format:

Outgoing claim type:

Outgoing name ID format:

☒ Pass through all claim values

☐ Replace an incoming claim value with a different outgoing claim value

Incoming claim value:

Outgoing claim value:  Browse...

☐ Replace incoming e-mail suffix claims with a new e-mail suffix

New e-mail suffix:

Example: fabrikam.com

< Previous Finish Cancel

Collect the needed information to complete the setup on the Awingu appliance

There are two properties that we will need during the configuration in Awingu:

- Relying Party Trust Identifier. This is the value chosen during the wizard setup of the relying party trust. This will correspond with the Entity ID configuration in Awingu
- Federation metadata. This can be found in the AD FS management tool under Service Endpoints Metadata Federation Metadata


The screenshot shows the AD FS management console. The left pane displays a tree view with 'Endpoints' selected under 'Service'. The main pane shows a table of endpoints. The 'Federation Metadata' entry is highlighted in blue. The right pane shows the 'Actions' menu for the selected entry, with 'View' and 'New Window from Here' visible.

Enabled	Proxy Enabled	URL Path	Type
Yes	Yes	/adfs/services/trust/wwi/wwiws	WS-Trust 2009
No	No	/adfs/services/trust/artifactresolution	SAML-ArtifactResolution
Yes	Yes	/adfs/oauth2/	OAuth
<b>Metadata</b>			
Yes	Yes	/adfs/services/trust/mex	WS-MEX
Yes	Yes	/FederationMetadata/2007-06/FederationMetadata.xml	Federation Metadata
Yes	No	/adfs/fs/federationsservice.smx	ADFS 1.0 Metadata
<b>OpenID Connect</b>			
Yes	Yes	/adfs/.well-known/openid-configuration	OpenID Connect Discover
Yes	Yes	/adfs/discovery/keys	OpenID Connect JWKS
Yes	Yes	/adfs/userinfo	OpenID Connect UserInfo
<b>Proxy</b>			
Yes	No	/adfs/proxy/	Web Application Proxy
Yes	No	/adfs/proxy/EstablishTrust/	Web Application Proxy
<b>Device Registration</b>			
Yes	Yes	/EnrollmentServer/	Device Registration
<b>WebFinger</b>			

## Setting up ADFS with OPSWAT as external IDPs for Awingu

Next to setting up Awingu with a single IDP like ADFS. It is also possible to setup Awingu in combination with multiple, chained, IDP's.


In this case we are going to configure Awingu in combination with ADFS for the user validation part and then with OPSWAT to validate the device. For more information on OPSWAT have a look at <https://docs.opswat.com/macloud-sdp>



Before you start with this setup please make sure that first Awingu in combination with ADFS is working. If this is working we can then extend the setup to add OPSWAT into the configuration. See [Setting up ADFS as an external IDP for Awingu](#) for instructions on this.

### Step 1: Export the token-signing certificate from your ADFS

Login to the ADFS configuration panel, goto Services Certificates and select the "Token-signing" certificate. Under details you will see an option to "copy to File" and export the certificate in a "Base-64 encoded" format.



### Step 2: Configure OPSWAT

If not yet done add your ADFS as an "Identity Provider": Login to your OPSWAT console and under "Secure Access" "Access Methodes" add select "Create New Identity Provider".

When asked for the IdP Certificate upload the ADFS certificate downloaded in the previous step.

OPSWAT.  
MetaAccess

Trust no file. Trust no device.

Dashboard

Secure Access

You have no active SDP Gateways. Activate at least one SDP Gateway to allow your users to connect to your applications through SDP.

Access Methods

Now add in OPSWAT a new protected application:

Select "Secure Access" "Protected Apps" "Add Protected App".

When asked for the method select: "IDP Setup" and select in the dropdown list your ADFS IDP you have added in the step before.

Use following parameters:

- **Application Name:** Free text.
- **IDP:** if not yet done select the ADFS IDP added in the step before
- **Access Methode:**
  - select Enforce if you want to make sure only trusted devices can login
  - select Monitor if you want to only log the connections from non-trusted devices
- **IdP login URL:** Set this value to <https://<your.adfs.url>/adfs/ls/IdpInitiatedSignOn.aspx?loginToRp=<RelayingPartyTrust>>

RelayingPartyTrust can be found on the ADFS configuration and is the identifier of this ADFS Relaying Party Trust. So for example set the URL to : <https://adfs.mycompany.com/adfs/ls/IdpInitiatedSignOn.aspx?loginToRp=awingu>

- **App ACS URL:** Set this to the value you can find in Awingu under "configure" "user connector" "federated authentication" "ACS URL"

In most cases this will be something like <https://<your.awingu.ul>/api/saml/>

Once the application is added you will get 2 sets of information back from OPSWAT:

1. An ACS URL that needs to be added to the Identity provider. The URL looks like [https://cac.opswat.com/nac/XXXXXXXXX/check/<your\\_app>](https://cac.opswat.com/nac/XXXXXXXXX/check/<your_app>)



2. An OPSWAT Certificate. Download the certificate to your local computer

### Step 3: Add the OPSWAT ACS URL to ADFS


Go back to the ADFS configuration and rightclick on the relying party trust and select "properties".

Goto the "Endpoints" tab and click on "Add SAML"

Select "Endpoint Type": SAML Assertion Consumer & "Binding": POST

Set the Index to 1

Set the Trusted URL to the ACS URL received when creating the OPSWAT protected app ( [https://cac.opswat.com/nac/XXXXXXXXXX/check/<your\\_app>](https://cac.opswat.com/nac/XXXXXXXXXX/check/<your_app>) )



### Step 4: Configure Awingu

Last thing to do now is to modify the existing ADFS SAML configuration on Awingu from simple "SAML" to "SAML with intermediate IDP"

Goto the Awingu system settings Configure User Connector Federated Authentication.

Select from the "protocol" dropdown list "SAML with Intermediate IDP".

You will notice that 2 extra fields become visible:

- Intermediate ACS URL: Set this to the same ACS URL received when creating the OPSWAT protected app (same as the one added in the step before in ADFS).
- Intermediate Signing Certificate: upload the certificate you received when creating the OPSWAT protected app.

**Intermediate ACS URL**  
The ACS URL of the intermediate IdP:

**Intermediate Signing Certificate**  
 No file chosen  
X 509 certificate in PEM format, used to verify the SAML response of the Intermediate IdP.

Check if all fields that were previously filled in with the standard ADFS settings are still filled in as before and if so click on "Apply".

### Step 5: Test if it works

Now open an in-private browser window. Go to the Awingu URL

If things are correct configured you should be redirected to ADFS.

After successful login ADFS will send you to OPSWAT.

After successful device validation in case of "enforced" mode you will be redirected to Awingu. In case of "monitor" mode you will see for a few seconds OPSWAT spinner and then arrive on Awingu.



If in Awingu the federated authentication is set to Single sign-on you will arrive directly in the workspace. If it is set to pre-authentication you will have to provide your windows password to get in.

## Setting up Google as an external IDP for Awingu

OpenID Connect pre-authentication can be configured with Google as the identity provider. The following instructions will show how to configure this in Awingu and in Google.

Register a new

1. Login to the Google Developers console and go to the credentials API page: <https://console.developers.google.com/apis/credentials>
2. First we need to add the domain on which Awingu is hosted is to the list of Authorized Domains  
Select *OAuth consent screen* *Authorized Domains*  
Add your domain to the list of authorized domains. (for example if your awingu is hosted on awingu.company.com, add company.com to the list)

Click on **Save** at the bottom of the page.

See <https://support.google.com/cloud/answer/6158849?hl=en&authuser=2#authorized-domains> for more details

3. Now we can add Awingu as an OpenID Connect client in Awingu  
Select *Create Credentials* *OAuth Client ID*

**Application Type:** Web application

**Name:** Display name of these credentials in the Google Developers console

**Authorized Redirection URLs:** <https://awingu.company.com/api/sso/> where "[awingu.company.com](https://awingu.company.com/)" points to your Awingu Environment. (Make sure to add the trailing slash)

Click on **Save** at the bottom of the page.

← Create OAuth client ID

For applications that use the OAuth 2.0 protocol to call Google APIs, you can use an OAuth 2.0 client ID to generate an access token. The token contains a unique identifier. See [Setting up OAuth 2.0](#) for more information.

**Application type**

- ☒ Web application
- ☐ Android [Learn more](#)
- ☐ Chrome App [Learn more](#)
- ☐ iOS [Learn more](#)
- ☐ Other

**Name** ⓘ

Awingu

**Restrictions**

Enter JavaScript origins, redirect URIs, or both [Learn More](#)

Origins and redirect domains must be added to the list of Authorized Domains in the [OAuth consent settings](#).

**Authorized JavaScript origins**

For use with requests from a browser. This is the origin URI of the client application. It can't contain a wildcard ([https://\\*.example.com](https://*.example.com)) or a path (<https://example.com/subdir>). If you're using a nonstandard port, you must include it in the origin URI.

<https://www.example.com>

Type in the domain and press Enter to add it

**Authorized redirect URIs**

For use with requests from a web server. This is the path in your application that users are redirected to after they have authenticated with Google. The path will be appended with the authorization code for access. Must have a protocol. Cannot contain URL fragments or relative paths. Cannot be a public IP address.

<https://awingu2.daas.com/api/sso/>

<https://www.example.com>

Type in the domain and press Enter to add it

Create Cancel

See <https://developers.google.com/identity/protocols/OAuth2> for more details

Collect the needed information to complete the setup on the Awingu appliance

There are 3 properties that we will need from the Azure Application during the configuration in Awingu:

- **Client ID** and **Secret** are provided by the Google API after finishing the above setup.
- The **Discovery URL** for Google is:

`https://accounts.google.com/.well-known/openid-configuration`

## Enabling Single Sign-On (SSO)

**i** Before enabling Single Sign-On (SSO) first make sure that the **pre-authentication is working** with your external identity provider (IDP).  
See "[Enable Pre-Authentication](#)" for detailed instructions on how to do this.

By enabling SSO in Awingu, the step where the user is prompted for their Microsoft Windows password prior to opening the Awingu workspace will be removed. This requires a trusted X.509 client certificate so users can log on to applications, virtual desktops and drives.

The certificate will be used to:

1. Generate a Kerberos ticket to
  - a. Log on to the Microsoft Windows domain (NLA)
  - b. Access the CIFS drives
2. Generate a virtual smartcard to allow RDP login (win-logon)

The Awingu appliance will act as a sub-certificate authority (sub-CA) and will automatically generate and manage those client certificates. In order to generate those certificates, Awingu requires an Active Directory signed certificate and private key that is trusted by all Microsoft Windows servers that require Awingu SSO access.



## Configure the bind user

To fill in some required information for the client certificates, a **bind user** must be specified in order to retrieve this information from the Active Directory. Navigate to System Settings > Global > Domains, select the relevant domain and fill in the username and password for the bind user.

## Generate Certificate and set up the intermediate sub-CA

Create the certificate

On the Microsoft Windows Domain Controller, create the "awingu.inf" certificate template with the following content. This can be done using Notepad or any other text editor.

```
[NewRequest]
Subject = "CN=AwinguCA"
KeyLength = 4096

[RequestAttributes]
CertificateTemplate= SubCA
```

Use **certreq** to request certificates from the certification authority (CA).

```
certreq.exe -new awingu.inf awingu.req
certreq -submit awingu.req awingu.cer
```


See [https://docs.microsoft.com/en-us/windows-server/administration/windows-commands/certreq\\_1](https://docs.microsoft.com/en-us/windows-server/administration/windows-commands/certreq_1) for more details.

Import the certificate into the certificate stores

In the next step, the certificate will be imported into the AD certificate store.

Run **certlm.msc** and import the certificate:

- Select the **Intermediate certificate store > Certificates**
- Go to **Actions > All Tasks > Import**
- Run through the wizard and import the awingu.cer file



Once this is done, the Active Directory needs to be configured to allow smart card logins that are signed with this intermediate certificate. As these client certificates will be generated by the Awingu CA (and as such be signed with this intermediate certificate), this certificate needs to be added to **NTAuthStore** of the Active Directory:

```
certutil -dspublish -f awingu.cer NTAuthCA
certutil -enterprise -addstore NTAuth awingu.cer
```

See <https://support.microsoft.com/en-us/help/295663/how-to-import-third-party-certification-authority-ca-certificates-into> for more information.

Check if the import was successful by running the following command:

```
certutil -enterprise -viewstore NTAuth
```

Both the AD root certificate and the intermediate Awingu certificate should be visible. Click on "more choices" to see all certificates.



#### Export Certificates and private key

To enable SSO in Awingu 2 files are needed:

1. The intermediate certificate in .pfx format, including the private key.
2. The root certificate of the AD in .cer format. This is needed to complete the certificate chain trust.

#### *Export the intermediate Certificate (with private key) in pfx format:*

To get the intermediate certificate we need to open certlm.msc again:

- Select the **Intermediate Certification Authorities store > Certificates**
- Right-click on the subca certificate (in this case AwinguCA) and select **All tasks > export**
- The export wizard will start
  - Select "Yes, export the private key" on the second page
  - Select "Personal Information Exchange - PKCS # 12 (.PFX) as format. Leave default settings ("include all certificates in the certification path if possible" + "enable certificate privacy")
  - Set a password on the certificate.
  - Finally on the "File to Export" page set the output file to subca.pfx
  - Finish the wizard.

#### *Export Root Certificate (without private key)*

To get the root certificate we need to open certlm.msc again:

- Select the **Trusted Root Certification Authorities store > Certificates**
- Right click on the root certificate of your AD and select **All tasks > Export** (in case you don't know what the root certificate of your AD is, open the intermediate certificate first and check the **certification path**. The certificate that has signed the intermediate certificate is the certificate that is needed)

- The export wizard will start
  - On the "Export File Format" page select "Base 64 encoded X.509 (.cer)"
  - Finally on the "File to Export" page set the output file to root.cer
  - Finish the wizard

**Important:** Check the entire **certification path** of the Awingu SubCA. If this is signed by one or more intermediate certificates and then by a root CA, it's necessary to export **each** of those intermediate certificates and the root CA in the same way as documented above for the root certificate. Copy-paste the contents of each exported .cer file below each other into one single file (do not include empty lines). Save the result to a single root.cer file.

Awingu must also trust the certificates used for Kerberos authentication of each Kerberos domain controller. Export any intermediate/root CAs in their certification paths which weren't already included in the root.cer file above.

## Validate if the Microsoft Windows back end is correctly configured for Awingu SSO

Validate the Kerberos Certificates

Awingu SSO is partly based on Kerberos Constrained Delegation (KCD). To make this work, the Kerberos setup needs to be done correctly.

If this is the first time KCD is used on this Windows back-end, there is a possibility that there is no Kerberos Certificate yet.

To check if there is a (valid) Kerberos certificate, open the certlm.msc again:

- Select the *Personal* store > *Certificates*
- Check if one of the AD certificates (certificates with the name of the Domain Controller) has a valid certificate with "Intended Purposes" set to "KDC Authentication"



If there is no valid certificate, add one first:

- Go to *Personal* > *Certificates*
- Right click on *Certificates* > *All tasks* > *Request New Certificate*
- Click next until you reach what kind of template to use, then select Kerberos

Check DNS setup

As Kerberos is highly dependent on DNS, DNS also needs to be configured correctly. In order for Awingu SSO to work, all of the DNS records for the servers defined in the drives, app servers and AD/LDAP server sections of the Awingu configuration need to be accessible with a reverse DNS lookup of its IP.

To check if this is the case do a DNS lookup of the DNS names used in Awingu for AD and other servers and check if the reverse lookup of the IP matches that name:

```
C:\Users\win-admin>nslookup awingu-ad.company.local
Name: awingu-ad.company.local
Address: 10.7.0.4
```

```
C:\Users\win-admin>nslookup 10.7.0.4
Name: awingu-ad.company.local
Address: 10.7.0.4
```

For reverse lookups of IP addresses Awingu uses the global DNS server, so not the DNS servers of the individual tenants. If you have a multi tenant setup with different DNS settings for the global appliance and for the individual tenants please validate on the Awingu appliance itself if the resolution of the reverse lookup is done correct for the tenants on which you want to enable SSO. This can be done via the troubleshoot page (*Global Troubleshoot*) and then select the "dig" action. In the "argument" field set "-x your.ip" (for example -x 10.1.2.3). If resolution is configured correctly, in the answer section you should see something similar:

```
;; ANSWER SECTION:
3.2.1.10.in-addr.arpa. 3600      IN      PTR      server.company.
local
```

Also check if the kerberos SRV records exist for your domain and that they point to the correct KDC. Check both the UDP & TCP records

```
C:\Users\win-admin>nslookup
> set type=srv
> _kerberos._udp.company.local

_kerberos._udp.company.local SRV service location:
        priority = 0
        weight = 100
        port = 88
        svr hostname = awingu-ad.company.local
awingu-ad.company.local internet address = 10.7.0.4

> _kerberos._tcp.company.local

_kerberos._tcp.company.local SRV service location:
        priority = 0
        weight = 100
        port = 88
        svr hostname = awingu-ad.company.local
awingu-ad.company.local internet address = 10.7.0.4
```

Update the DNS records where needed (reverse lookup + SRV records) to ensure this is working correctly before continuing.

Make sure all servers involved in Kerberos Authentication can access the Certificate Revocation List

HTTP(s): TCP port 80/443 connectivity from the Active Directory and Application Servers to the Awingu appliance (`http(s)://<AWINGU_URL>/crl/>AWINGU_DOMAIN_NAME`) is required.

Make sure LDAPs is enabled on the Active Directory

Similarly to Kerberos, for an LDAPs connection a valid Certificate is needed on the Active Directory:

To check if there is at least one (valid) Domain Controller certificate open the `certlm.msc` again:

- Select the *Personal* store > *Certificates*
- Check if one of the AD certificates (certificates with the name of the Domain Controller) has a valid certificate with "Intended Purposes" set to "Client Authentication" and "Server Authentication"



For more information on how to set this up take a look at our support portal: <https://support.awingu.com/en/support/solutions/articles/8000055177-tutorial-00-enable-active-directory-over-ssl>

Make sure the Connection Broker Session Collection is configured for smart cards

When using an RDS Connection Broker Session Collection, then the session needs to have smart card redirection enabled from the client device:

- Open server manager and go to the RDS Session Collection
- Next to "Properties" in the RDS collection > Tasks > Edit Properties > Client Settings: Ensure "Smart cards" is ticked under "Enable redirection for the following:"



Configure Awingu for SSO

**i** Only if the following conditions are met, Awingu SSO can be enabled:

1. The sub-CA certificates have been created (root.cer, awingu.cer and awingu.key)
2. All dependencies on the Microsoft Windows back end have been set up (import of the sub-CA certificate in the correct stores, Kerberos and DNS configuration, etc.)
3. Pre-authentication with the external IDP has been configured and tested (see [Enable Pre-authentication](#))

#### Enable the Awingu Key Vault

Since the private key for the Awingu Sub-CA allows Awingu to impersonate Microsoft Windows users, this key is highly sensitive and is stored in a vault inside Awingu. The vault itself is also encrypted and the encryption key for the vault can either be stored on the Awingu appliance itself (Internally) or on an external Vault provider like Google Cloud Key Management Service or Azure Key Vault.

By default the Vault is not activated and needs to be enabled first:

- Open the System Settings and go to *Global Connectivity Vault*
- Select the provider of choice
- Click on Apply.

Enabling the vault might take a few minutes.



For more information on the external Vault providers and how to obtain the needed configuration parameters have a look at:

- Azure Key Vault: <https://docs.microsoft.com/en-us/azure/key-vault/key-vault-overview>
- Google Cloud Key Management Service (GCKMS): <https://cloud.google.com/kms/docs/quickstart> . When using the Google Cloud Key Management Service (as an external Vault Provider, the GCE Service Account requires these permissions:
  - Cloud KMS Viewer
  - Cloud KMS CryptoKey Encrypter/Decrypter

**i** The private key itself does not leave the vault. After the initial upload, it only exists in unencrypted form in the memory of the vault service.

If the Awingu appliance running the vault services is rebooted, access to an external vault provider such as Google GCKMS or Azure Key Vault is required to unseal the vault and decrypt the private key.

Since the vault does not allow extracting the private key, certain configuration changes of the Awingu environment result in a full vault reset, which will disable SSO and require you to re-upload the private key of the CA.

These are:

- Restoring a database backup (only applicable if using Awingu with an internal database)
- Changing the vault provider

For HA purposes, the vault service is replicated across all back-end nodes in an Awingu environment.

*If not yet done, set the domain parameters correctly:*

When adding a domain to Awingu one of the parameters is specifying if the LDAP connection is over SSL or not.

If this has not yet been done make sure this is enabled;

- Open the System Settings and go to *Global Domains*
- Click on the "edit" button next to the domain you want to check.
- In the *domain details* check if *LDAP over SSL* is set to **enabled**

Also make sure that:



1. The FQDN of the domain is set to the Kerberos realm of the Windows Domain (example: company.local)
2. The AD/LDAP server is set to the correct FQDN of the domain controller (example: ad1.company.local). Awingu won't work if the IP address or an alias is used.

If not yet done, make sure Awingu is using the correct DNS server

Awingu has DNS servers on 2 levels. One for the appliance itself and one for the tenants/domains.

As the Global DNS server is used for reverse DNS resolution, make sure that the Global DNS server is pointing to a DNS server that is capable of resolving all reverse DNS lookups for all tenants/domains using SSO.

To check and modify the global DNS server:

- Open the System Settings and go to *Global Connectivity Servers*
- Point the *DNS IP Addresses* to the correct DNS server(s).

If not yet done, set Authentication Protocol of Application servers to Kerberos

When adding an application server, the default Authentication Protocol is NTLM. For SSO to work, Awingu needs to use Kerberos.

To switch application servers from NTLM to Kerberos:

- Open the Awingu System Settings and go to *Manage > Application Servers*
- Switch the Authentication Protocol from *NTLM* to *Kerberos*
- Make sure the *Authentication Host* is set to the FQDN of the server and that the name specified in here matches the DNS and reverse DNS name

Make sure you set this value for all application servers that Awingu uses with SSO.

Upgrade from Pre-Authentication to Single Sign-On

Now that all settings both on the Microsoft Windows back end and the Awingu appliance are set, update the configuration to switch from Pre-Authentication to SSO.

- Open the System Settings and go to *Configure > User Connector > Federated Authentication*
- Change the Type from *Pre-Authentication* to *Single sign-on*
- You will notice that below the existing Pre-Authentication configuration 2 extra certificate settings will appear: *CA Certificate* and *CA Trusted Roots File*



- Select *Manual PKCS 12* as the type for CA Certificate and upload the "subca.pfx" file + set the CA certificate password to the password set on the PFX certificate earlier.
- Select *Manual PEM* as the type for CA Trusted Roots and upload the "root.cer" file. (Note: When updating this certificate, the CA Certificate also needs to be re-uploaded)
- Test both certificates by clicking on "Show certificate". If there are no errors, you can continue.
- Verify that the Username Claim URL points to the UPN property of the SAML response. Single Sign-On can only work when using the UPN.
- Click Apply

Show Certificate

To validate if your certificate is correct, you can visualize the certificate's content using the *Show Certificate* button.

## End User Flow:

The end user flow will be similar to the one from Pre-Authentication except that the step where the user needs to enter their Windows Password again will no longer appear:

- When a user accesses the Awingu landing page, Awingu will check if the user has a valid authentication token with the configured IDP.
- If this is not the case yet, Awingu will redirect the browser to the IDP. User will need to authenticate first against the IDP. If successful, the IDP will redirect the User to the Awingu landing page.
- User will be logged into the Awingu Workspace
- From the Workspace, they can start Apps, Desktops and get access to the Drives.

From a technical point of view once a user has pre-authenticated, Awingu will now use the UPN that was received from the IDP to create a X.509 client certificate suitable for smart-card login. These client certificates are valid for 1 day. Using the client certificate, Awingu requests a Kerberos Ticket Granting Ticket (TGT) from the Active Directory Domain Controller through PKINIT. To complete the login to Awingu, Awingu fetches the

attributes and group memberships of the user from the Active Directory Domain Controller. These attributes are required for other functionality in Awingu to work, for example to decide if a user has admin rights or if the user is allowed access to certain drives, applications or features of Awingu.

In order to setup an RDP session using Awingu, we must perform two authentication steps, the network level authentication (NLA) and Windows logon:

- The NLA is done using the same Kerberos TGT acquired earlier. We currently support up to CredSSP version 6 for this authentication step.
- For the Windows logon, Awingu emulates a smart card designed to work with the Windows standard drivers. This virtual smart card appears to contain the X.509 client certificate that was generated earlier.

Note: When SSO is configured, the Change Password link in the Account Settings of the users will not be visible to avoid confusion about which password will be changed (IDP or AD).

# Microsoft OneDrive for Business

- [Introduction](#)
- [Allowing Awingu to access your Office 365 subscription](#)
  - [Step 1. Get an Office 365 subscription](#)
  - [Step 2. Set up an Azure Active Directory tenant](#)
  - [Step 3. Register your app with Azure Active Directory](#)
  - [Step 4. Have the network right](#)
- [Configuring Awingu to access OneDrive](#)
- [Configuring the Awingu OneDrive app](#)
- [Using OneDrive on Awingu](#)

## Introduction

Users of OneDrive for Business can have their home drive shown on the Files page in Awingu. They can do all actions as with normal drives, like upload, download, copy, move, rename, delete, preview, except of opening a file with a streamed application.

We describe in this section how to configure both your Microsoft account and your Awingu environment.

## Allowing Awingu to access your Office 365 subscription

In order to allow your Awingu environment to access the OneDrive of your Office 365 subscription, Microsoft provides following documentation:

 <https://dev.onedrive.com/app-registration.htm#register-your-app-for-onedrive-for-business>

That document is however somewhat outdated, so we summarize here the steps to take.

## Step 1. Get an Office 365 subscription

All Office 365 subscriptions for Small Businesses and Enterprises should be compatible with Awingu. Even the smallest package, Office 365 Business Essentials, works fine.

The procedure dictates to get an Office 365 Developer Site:

1. Go to <https://portal.office.com> > Admin
2. Resources > Sites
3. Click on "Add a site"
4. Fill in all the fields like you desire  
For following fields, please note:
  - Template Selection: Developer Site
  - Server Resources: default value should be enoughClick OK and you end-up in the SharePoint admin center (direct link: [https://<your\\_account>-admin.sharepoint.com](https://<your_account>-admin.sharepoint.com))
5. The new developer site URL in the Site Collections list.
6. When the site creation is finished (spinning wheel next to the URL), you can navigate to the URL to open your Developer Site.  
This takes a long time (up to one hour).

## Step 2. Set up an Azure Active Directory tenant

Make sure your Office 365 subscription is synced with Azure AD.

## Step 3. Register your app with Azure Active Directory

1. Go to <https://portal.azure.com>
2. Open the service: App registrations
3. Click on New registration:
  - a. Name: e.g. "OneDrive on Awingu"
  - b. Supported account types: Accounts in any organizational directory (Any Azure AD directory - Multitenant)
  - c. Redirect URI:
    - i. Web
    - ii. URL: the URL to your Awingu environment (e.g. <https://awingu.mycompany.com>)
4. Once created, retrieve the Client ID = Application ID.  
You will need this value to configure Awingu.
5. Click on Certificates & secrets and click New client secret
  - a. Description: secret

- b. Expires: Never
- c. Click on Save
- d. Retrieve Client secret = secret

You will need this value to configure Awingu.



The value cannot be retrieved afterwards. Don't lose it!

6. Click on API permissions and click on Add a permission:
  - a. Select an API: Office 365 SharePoint Online
  - b. Select permissions: Read and write user files (delegated permission)
  - c. Click on Done

## Step 4. Have the network right

Awingu needs to be able to reach the OneDrive for Business servers directly, or through an HTTP proxy (see [Connectivity Settings](#)). HTTPS (port 443) access is required to:

- <mydomain>-my.sharepoint.com
- graph.microsoft.com
- api.office.com

### Configuring Awingu to access OneDrive

OneDrive for Business can be configured as Drive in the System Settings. Go to Manage > Drives and add a drive with following settings:

- Name: e.g. OneDrive
- Description
- Backend: ONEDRIVE
- Client ID: see previous section
- Client secret: see previous section
- Workspace URL: the URL a user uses to access Awingu, e.g. <https://awingu.mycompany.com>
- Redirect URL: you will need this value to configure Azure Active Directory
- URL: link to your sharepoint.com environment, e.g. <https://mycompany.sharepoint.com>
- UNC: can be left empty
- Labels: you can use labels to group drives together. You can leave this empty.
- User Labels: the drive will only be visible for users with a matching user label. Use "all:" to assign the drive to all users.

### Configuring the Awingu OneDrive app

1. Go to <https://portal.azure.com>
2. Go to Azure Active Directory > App registrations
3. For your app (e.g. OneDrive on Awingu), go to Manage > Authentication
4. Under Web > Redirect URIs > add the Redirect URL you've obtained in System Settings
5. Press Save

### Using OneDrive on Awingu

When a user opens their OneDrive folder on the Files page in Awingu for the first time, they will be redirected to the Office login portal where access is requested to their OneDrive. Once access is granted, they can use OneDrive as any other folder in Awingu, except of opening a file with a streamed application (only open with Preview will work).

# Smart Card Redirection


## Introduction

Awingu supports accessing smart cards in streamed applications. This enables a user to access a smart card connected to his client device (e.g. a smart card reader in his laptop) from an application running on an application server. Typical use cases include electronic ID cards, banking cards or access cards. This does not include using smart cards as second factor authentication for accessing the Awingu portal.

Although any smart card should work, Awingu has explicitly tested the following smart cards:

- Belgian eID
- Dutch UZI pas
- Italian InfoCert Business Key
- Isabel

## How It Works



In order to use a smart card in a streamed application, the administrator should explicitly enable smart card support for the application and the user should be equipped with a smart card reader connected to his device. When the user launches such a smart card support enabled application, the Awingu portal will connect to the locally installed Remote Application Helper, which will connect to the smart card reader and act as a bridge between the smart card reader and the Awingu portal.

## Enabling smart card support

### Preparing the application server

The application server should have the middleware installed of the smart card.

### Enabling smart card access on Awingu

To enable smart card access to an RDP or RemoteApp application, the *smartcard*: label should be assigned to the application. This can be set in the details of an application in the *System Settings* under *Manage > Applications*

DEV-AWINGU
Configure
Manage
Changes
Global

Application Details

Name	eID Viewer	
Description	eID Viewer running on Application Server 2016	
Icon	'16	
Protocol	Remote Application	
Alias	eIDViewer	
Unicode Keyboard Support	Enabled	
Categories	Smartcard Windows 2016	
Media Types		
Labels	smartcard:	
Server Labels	appserver_group:win2016 smartcard	
User Labels	all:	

System Settings - © 2012-2018 Awingu N.V. - Eula
4.0.0

Once this label is assigned to an application, the application will try to connect to the Remote Application Helper.

## Enabling smart card access on the client

The first time a user launches a smart card enabled application, the browser will ask the user to download the Remote Application Helper. This software can be downloaded from the Awingu appliance and is available for Windows and macOS.

Note that for macOS, the installer is not signed: the user needs to do right-click > Open on the installer.

The user needs to have the drivers of the smart card reader installed on their device. Note that some drivers are included in the operating system and don't need any end-user intervention.

### Limitations

1. The smart card reader needs to be connected before opening the application.

2. The libraries to communicate with smart cards differ slightly between Windows and macOS. Therefore, it might be that some applications on the Windows application server will perform a certain library call that is incompatible with the macOS library available on the end-user device. We have seen this behavior for the eID Viewer and Isabel.
3. The Remote Application Helper will use a proxy on the client if it detects a configured proxy on Windows. The Remote Application Helper cannot be configured to use a proxy on macOS.

### Troubleshooting

- Check whether the driver of the smart card reader is installed on the user's device.
- Check whether the middleware of the smart card is installed on the application server.
- When Firefox has been installed after the installation of the Remote Application Helper, the Remote Application Helper needs to be re-installed.
- When the user did not stop Firefox during the installation (as requested in the installer), the Remote Application Helper needs to be re-installed.
- When using clients with Windows 7 Embedded, you will need to install [Visual C++ 2015 redistributable](#) (32-bit/x86 version) on them. It is a [known issue](#) that you need to install KB2999226 first to be able to install Visual C++ 2015.

## Automate Awingu via the REST API

Awingu provides a [REST API](#) allowing to install, configure and manage Awingu. This allows you to integrate Awingu in an automation framework.

- Getting Started with the Awingu API
  - PowerShell example using an API Token
  - Navigating Through the API
  - Changing Settings
  - Logging Out
  - Further documentation
- Installing with the Awingu API
- Configure using the Awingu API

## Getting Started with the Awingu API

This section assumes:

- You have an installed Awingu appliance running.
- You have a domain configured.
- You have the correct tools to execute REST API calls (e.g. PowerShell, see below).

To test it out manually, you can use `curl` as a tool to execute the REST API calls

- The live API browser at [http\(s\)://your-awingu-environment/api/v2/](http(s)://your-awingu-environment/api/v2/)
- The API documentation at [http\(s\)://your-awingu-environment/api/v2/docs/](http(s)://your-awingu-environment/api/v2/docs/)

Note: all API calls are addressed to **the workspace URL** of the appliance.

## PowerShell example using an API Token

If enabled for the domain, admin users can get an API token to interact with the REST API.

See [User Connector Configuration](#) for information on how to limit API token based authentication to certain subnets.

In order to get an API token, go to your **Account settings** and click **Manage API token**, which will show a dialog window for generating a token.

Awingu.com

Workspaces

Files

Applications

## Manage API token

Close

When automating the configuration by means of a REST API, it is possible to use a token to bypass logging in and the multi-factor authentication; you will not be prompted to fill in a username and password.

Only administrators can generate a token for their username. When generating a new token, the previous token is disabled.

Please refer to the Administration Manual for more information about REST API-based configuration.

**Warning:** A token is equivalent to a password and should therefore be kept secret. Anyone with a token has the same access rights and configuration permissions as the user who generated it.

Please enter your password to generate or disable a token:

Password

Generate new token

Generated token for dev-awingu/kenwyny:

Save

Generate new token

Disable token

❗ Note that API tokens continue to be valid even when the user was removed from Active Directory, or when removed from the admin group.



For an audit trace of the API tokens check **Changes** for your domain in **System Settings**, and filter on **Session Token** as **Resource Type**.

**Changes**

Filters: Action, Session Token, Resource Id, User, Authentication, From, To, Reset

Action	Resource Type	Resource Id	User	Authentication	Timestamp
✓ Create	Session Token	DEV-AWINGU - kenwyny	dev-awingu/kenwyny	Session	2018-10-27 19:53:00
✓ Create	Session Token	admin	admin	Session	2018-10-24 10:39:37
✓ Create	Session Token	DEV-AWINGU - kenwyny	dev-awingu/kenwyny	Session	2018-10-23 12:51:57
✓ Create	Session Token	DEV-AWINGU - kenwyny	dev-awingu/kenwyny	Session	2018-10-22 18:29:43
✓ Create	Session Token	admin	admin	Session	2018-10-21 19:33:38

10 items per page 1 / 1

Export CSV

**Changes Details**

Request: { "password": "\*\*\*\*\*" }

Response: { "token": "\*\*\*\*\*" }

System Settings - © 2012-2018 Awingu N.V. - Eula 4.1

With the API token you can consume the REST API from PowerShell as shown in the below example, listing all application servers:

```
$token = "<your API token here>"
$your_uri = "https://<address of your appliance here>/api/v2/app-servers/"

[Net.ServicePointManager]::SecurityProtocol = [Net.SecurityProtocolType]::Tls13

$headers = @{}
$headers.Add("Authorization", "Token $token")

$result = Invoke-RestMethod -Method get -Uri $your_uri -Headers $headers
$result.results | Format-Table
```

## Navigating Through the API

- To list the URIs to all available system resources:

```
URI:      /api/v2/
Method:   GET
```

```
Headers: Accept: */*
        Authorization: Token your-api-token
```

Expected response: 200 with following payload:

```
{
  "branding": "http://172.16.5.74/api/v2/branding/",
  "branding-images": "http://172.16.5.74/api/v2/branding-images/",
  "favicons": "http://172.16.5.74/api/v2/favicons/",
  "domains": "http://172.16.5.74/api/v2/domains/",
  "hostheaders": "http://172.16.5.74/api/v2/hostheaders/",
  "certificates": "http://172.16.5.74/api/v2/certificates/",
  "apps": "http://172.16.5.74/api/v2/apps/",
  "app-servers": "http://172.16.5.74/api/v2/app-servers/",
  "app-icons": "http://172.16.5.74/api/v2/app-icons/",
  "user-apps": "http://172.16.5.74/api/v2/user-apps/",
  "key-combos": "http://172.16.5.74/api/v2/key-combos/",
  "configuration": "http://172.16.5.74/api/v2/configuration/",
  (...)
}
```

- To retrieve an system resource, e.g. the drives, you can use the URI mentioned in the output of the previous command:

```
URI:      /api/v2/drives/
Method:   GET
Headers:  Accept: */*
        Authorization: Token your-api-token
```

Expected response: 200 with following payload:

```
{
  "count": 31,
  "next": null,
  "previous": null,
  "results": [
    {
      "backend": "CIFS",
      "config": [],
      "description": "Home Drive via CIFS",
      "domain": "http://172.16.5.74/api/v2/domains/2/",
      "name": "Home Drive",
      "unc": "\\fileserver\\Users$\\<username>\\Documents",
      "url": "smb://fileserver.mycompany.com/Users$/<username>
/Documents",
      "use_domain": false,
      "labels": [],
      "user_labels": [
        "all:"
      ],
      "uri": "http://172.16.5.74/api/v2/drives/1/",
    }
  ]
}
```

```

        "smb_max_protocol": "SMB3"
    },
    (...)
]
}

```

For more information about this resource, you can use your web browser to navigate to [http\(s\)://your-awingu/api/v2/docs/#drives](http(s)://your-awingu/api/v2/docs/#drives)

## Changing Settings

- To add a resource, e.g. to add a drive to a domain:

```

URI:      /api/v2/drives/
Method:   POST
Headers:  Content-Type: application/json
          Accept: */*
          Authorization: Token your-api-token
          Referer: http://your-awingu-env/
Payload:  {
    "domain": "http://172.16.5.74/api/v2/domains/2/",
    "name": "New Drive",
    "description": "This is a drive to test the API",
    "backend": "CIFS",
    "config": [],
    "url": "smb://fileserver.mycompany.com/TestShare",
    "unc": "\\fileserver\\TestShare",
    "use_domain": false,
    "labels": ["testkey:testlabel"],
    "user_labels": ["all:"]
}

```

Expected response: 201, with the URI of the drive in the payload.

Note that the API will automatically create the labels and user\_labels provided in case they don't exist. You can verify this in `/api/v2/labels/`

- To change fields of an existing resource, e.g. change the unc field of a drive:

```

URI:      /api/v2/drives/9/
Method:   PATCH
Headers:  Content-Type: application/json
          Accept: */*
          Authorization: Token your-api-token
          Referer: http://your-awingu-env/
Payload:  {"unc": "\\fileserver\\Share"}

```

## Logging Out

```

URI:      /api/v2/sessions/current/
Method:   DELETE
Headers:  Accept: */*
          Content-Type: application/json

```

```
Authorization: Token your-api-token
Referer: http://your-awingu-env/
```

Expected response: 204

## Further documentation

All available API resources are documented on your appliance on `/api/v2/docs/`.

### Installing with the Awingu API

1. Deploy the Awingu appliance and configure the networking, which can be automated with the API tools provided by the virtualization or cloud platforms in combination with DHCP.
2. Once the VM has been started, the installer API will start to listen on **port 8080**.
3. To start the installation, do following call on port 8080. Please refer to [Awingu Installer](#) for more information about the fields used in the request.

```
URI:      /api/v2/updates/install/
Method:   POST
Headers:  Accept: */*
          Content-Type: application/json

Payload:  {
    "config": {
      "eula": {
        "accepted": true
      },
      "network": {
        "dns": "172.19.0.1",
        "ntp": "ad.mycompany.com"
      },
      "environment": {
        "management_user": {
          "username": "my-admin-user",
          "password": "my-password",
          "confirmed_password": "my-password"
        }
      },
      "appliances": [
        {
          "ip_address": "172.19.0.2",
          "hostname": "awingu"
        }
      ],
      "features": {
        "common": {
          "external_database": false
        }
      }
    }
  }
```

Expected response: 201 with payload:

```
{
  "uri": "http://172.16.5.76:8080/api/v2/updates/1/",
  "progress": [],
  "begin": "2017-10-20T11:04:24",
  "end": null,
  "status": "IN_PROGRESS",
  "service": null,
  "version": "http://172.16.5.76:8080/api/v2/versions/1/",
  "outputs": "http://172.16.5.76:8080/api/v2/update-outputs/?update=1"
}
```

4. Wait until the installer has finished:

```
URI:      /api/v2/updates/1/
Method:   GET
Headers:  Accept: */*
```

If field "status" can be IN\_PROGRESS, SUCCEEDED or FAILED.  
The error output can be retrieved via the outputs field of the response:

```
URI:      /api/v2/update-outputs/?update=1
Method:   GET
Headers:  Accept: */*
```

## Configure using the Awingu API

Once the installation is done, you can configure Awingu as follows:

1. Enable an API token for the management user configured during the installation.
2. Add your first domain via POST to `/api/v2/domains/`.  
Hostheaders are autogenerated if you provide a list of FQDNs in the "hostheaders" field.  
The user connector is configured in the same domain resource.
3. User groups, like for admin, are added via `/api/v2/user-groups/`
4. Application servers are added via `/api/v2/app-servers/`  
For each application server, a server label is automatically created and linked to it.
5. Icons for applications are uploaded via `/api/v2/app-icons/create/`
6. Applications are added via `/api/v2/apps/`, where you need to provide the link to the uploaded app-icon.  
Provided labels (labels, user\_labels, server\_labels) and categories are automatically created if they don't exist yet.
7. Drives are added via `/api/v2/drives/`.  
Provided labels (labels, user\_labels) are automatically created if they don't exist yet.

Please refer to the documentation on `/api/v2/docs/` to have more information of the payload to provide.

## External Audit Logging

- [Introduction](#)
- [Structure](#)
- [Audit Records Types](#)
  - [User Sessions](#)
  - [Application Sessions](#)
  - [Web Application Sessions](#)
  - [Application Gateway](#)
  - [File Actions](#)
  - [Shares](#)
  - [Shared Application Session](#)
  - [Shared Application Session Settings](#)
  - [IdP Sessions](#)
  - [Anomalies](#)

### Introduction

Awingu allows you to forward all audit logs to an external system using the HTTP(S) protocol.

Each record will be transmitted to the configured URL using an HTTP POST per record in JSON format.

### Structure

A record is a collection of unordered key/value pairs (an `Object` in JSON terms) providing information of the audit event for the specific `audit_type`.

All records provide the following properties:

Property	Type	Description
<code>audit_type</code>	String	The audit record type
<code>version</code>	String	Awingu version

Based on the `audit_type` you can discriminate between audit record types and interpreter the specific properties of each type.

The `version` field represents the Awingu version and allows you to version your integrations.

### Audit Records Types

#### User Sessions

*User Session* records represent a single authenticated session between a browser and the Awingu environment for a user. If a user logs in for a second time on a different browser, this will result in a new session.

User sessions are also the basis for licensing, e.g. the number of concurrent users is determined based on the number of simultaneous active sessions.

Property	Type	Description
<code>audit_type</code>	String	Record type ( <code>usersessions</code> )
<code>version</code>	String	Awingu version
<code>session_id</code>	String	Unique id
<code>session_start</code>	DateTime	Timestamp when the session started in UTC
<code>session_end</code>	DateTime	Timestamp when the session ended in UTC
<code>session_labels</code>	String	A comma-separated list of all labels assigned to the user for this session
<code>username</code>	String	Username
<code>domain</code>	String	Name of the Awingu domain
<code>ip</code>	String	The IP address of the client that created this session
<code>http_agent</code>	String	Value of the <code>User-Agent</code> header when creating this session

country	String	Country from where the session was created based on GeoIP
geoip_latitude	String	Latitude from where the session was created based on GeoIP
geoip_longitude	String	Longitude from where the session was created based on GeoIP
name	String	Browser name based on User-Agent
major	String	Browser version major based on User-Agent
minor	String	Browser version minor based on User-Agent
os	String	Client operating system based on User-Agent
os_name	String	Client operating system name based on User-Agent

## Application Sessions

*Application Sessions* represent a single streamed application or desktop session for a user. Every time a new streamed application or desktop connection is started, a new application session is generated.

 Web applications and reverse proxied web applications are logged separately as Web Application Sessions

Property	Type	Description
audit_type	String	Record type (appsessions)
version	String	Awingu version
userapp_session_id	UUID	Unique id
user_session_id	String	Reference to the <i>User Session</i> that started the <i>Application Session</i>
ip	String	The IP address of the client starting the application
appsession_start	DateTime	Timestamp when the application session started in UTC
appsession_end	DateTime	Timestamp when the application session ended in UTC
app_key	UUID	Identifier of the application started
domain	String	Name of the Awingu domain the application is configured
server	String	Host name of the application server the application is started on
port	String	The port on the application server used to start the application
exe	String	The alias of the RemoteApp (empty for RDP applications)
recorded	Boolean	Indicated if the <i>Application Session</i> is recorded or not
rdpgw_session_id	UUID	The internal id for the connection between the browser and Awingu
rdpgw_numeric_id	String	The internal id for the connection between the browser and Awingu

## Web Application Sessions

*Web Application Sessions* represent web applications launched from the Awingu portal or access to a reverse proxied web application using the configured source host header or launched from the Awingu portal.

Property	Type	Description
audit_type	String	Record type (webappsessions)
version	String	Awingu version
user_session_id	String	Reference to the <i>User Session</i> that started the <i>Web Application Session</i>
timestamp	DateTime	Timestamp when the <i>Web Application Session</i> started in UTC

url	String	URL used to access the web application
name	String	Name of the web application configured
domain	String	Name of the Awingu domain the web application is configured
reverse_proxy	Boolean	Indicated if the web application started is a reversed proxied web application

## Application Gateway

The Application Gateway is an internal component that determines a.o. on which application server an application can be started and also keeps track of the status of all application sessions. It manages both *Application Sessions* and *Web Application Sessions*.

The audit records of this component allow you to track changes in the state of all application sessions.

Property	Type	Description
audit_type	String	Record type (appgw)
version	String	Awingu version
timestamp	DateTime	The timestamp of the status change
username	String	Username of the user owning the application session
session_id	UUID	Reference to the <i>User Session</i> that started the <i>Web Application Session</i>
session_labels	String	A comma-separated list of all labels assigned to the user for the referenced <i>User Session</i>
domain	String	Name of the Awingu domain the application is configured
appname	String	Name of the application
appkey	UUID	Identifier of the application
labels	String	A comma-separated list of all labels assigned to the application
user_labels	String	A comma-separated list of all user labels assigned to the application
server_labels		A comma-separated list of all server labels assigned to the application
appsession_id	UUID	<i>Application Session</i> id
status	String	New status of the application session
host	String	Host name of the application server the application is started on
gateway_id	String	Name of the Awingu appliance handling the application session
document	String	UNC path to the document opened with the application

## File Actions

A *File Action* represents a file operation executed through the Awingu portal, this does not include file operations executed by streamed applications.

Property	Type	Description
audit_type	String	Record type (file_actions)
version	String	Awingu version
timestamp	DateTime	The timestamp of the action
session_id	UUID	Reference to the <i>User Session</i> that executed the file action
action	String	Action executed on the file
domain	String	Name of the Awingu domain the drive is configured



drive	String	Name of the drive the file action was executed on
destination_drive	String	Name of the destination drive if the file action results on another drive
file_path	String	The relative path of the file on the drive
destination_file_path	String	The relative path of the file on the destination drive if the file action results on another drive

## Shares

Property	Type	Description
audit_type	String	Record type (shares)
version	String	Awingu version
timestamp	DateTime	The timestamp of the action
session_id	UUID	Reference to the <i>User Session</i> that executed the file action
action	String	Action executed on the share
domain	String	Name of the Awingu domain the share is configured
share_id	UUID	Unique ID of the share
share_name	String	Name of the share
share_content_type	String	Content-type of the share
share_expires	DateTime	The expiry date of the share
share_drive	String	Name of the drive the share is part of
share_domain	String	Name of the Awingu domain the share is configured
share_created_by	String	Username of the user that created the share
share_path	String	The relative path of the file on the drive
share_mode	String	Availability mode of the share
share_is_public	String	Is the share publicly available
share_access_rights	String	How are the access rights determined?
share_access_labels	String	Which users/groups can access the share when <code>share_access_rights</code> is <code>USER</code>
share_checksum	String	The checksum of the shared file (when accessed)
share_has_password	String	Is the share password protected
ip	String	The IP address of the client performing the action
country	String	The country based on GeoIP of the client accessing the share
geoip_latitude	String	The latitude based on GeoIP of the client accessing the share
geoip_longitude	String	The longitude based on GeoIP of the client accessing the share
range	String	Range accessed during request

## Shared Application Session

A *Shared Application Session* represents a guest that joined or leaves a shared application session.

Property	Type	Description
audit_type	String	Record type (sharedappsessions)

version	String	Awingu version
userapp_session_id	UUID	Reference to the <i>Application Session</i> that is shared
sharedappsession_start	DateTime	The timestamp on which the client joined the shared application session
sharedappsession_end	DateTime	The timestamp on which the client left the shared application session
rdpgw_session_id	String	The internal id for the connection between the browser (guest) and Awingu
rdpgw_numeric_id	String	The internal id for the connection between the browser (host) and Awingu
ip	String	The IP address of the client that joined the shared application session
domain	String	Name of the Awingu domain the application session is part of

## Shared Application Session Settings

A *Shared Application Session Setting* represents a change in the configuration of a shared application session.

Property	Type	Description
audit_type	String	Record type (sharedappsessions_settings)
version	String	Awingu version
timestamp	DateTime	The timestamp of the action
user_session_id	String	Reference to the <i>User Session</i> that started the <i>Application Session</i>
userapp_session_id	UUID	Reference to the <i>Application Session</i> that is shared
rdpgw_session_id	UUID	The internal id for the connection between the browser (guest) and Awingu
joinable	Boolean	Is the application session shared
isProtected	Boolean	Is the shared application session password protected
joinMode	String	always SINGLE
accessRights	String	Is the session shared in PUBLIC or DOMAIN mode
host	String	The hostname of the Awingu appliance handling the application session
domain	String	Name of the Awingu domain the application session is part of

## IdP Sessions

IdP Sessions represent Awingu acting as IdP for web applications and confirming a user's identity based on the Awingu session.

Property	Type	Description
audit_type	String	Record type (idpsessions)
version	String	Awingu version
login_time	DateTime	The timestamp an external SSO Service requests Awingu to identify a user
logout_time	DateTime	The timestamp the <i>Users Session</i> ended
user_session_id	String	Reference to the <i>User Session</i> for which the SSO Service requests was made
username	String	The username for which the SSO Service requests was made
service_provider_name	String	Name of the service provider, as mentioned in <a href="#">User Connector Configuration</a>

domain	String	Name of the Awingu domain the <i>User Session</i> is part of
assertion_consumer_service	String	ACS URL, as configured for the SSO service
request_issuer	String	The issuer, as configured for the SSO service
request_id	String	SAML request ID, provided by the SSO service

## Anomalies

An anomaly represents an unusual activity detected by the Awingu environment. More information on the type of anomalies can be found in [Anomaly Reporting](#).

Property	Type	Description
audit_type	String	Record type (anomalies)
version	String	Awingu version
timestamp	DateTime	The timestamp of the event
session_id	String	Reference to the <i>User Session</i> if the user is logged in
code	String	Anomaly code
category	String	Anomaly category
description	String	Anomaly description
username	String	The username used for the login
domain	String	Name of the Awingu domain the <i>User Session</i> is part of
http_agent	String	The <i>User-Agent</i> header of the client
ip	String	The IP address of the client
country	String	The country based on GeoIP of the client
geoip_latitude	String	The latitude based on GeoIP of the client
geoip_longitude	String	The longitude based on GeoIP of the client
fingerprint	String	The generated fingerprint of the client (NEW_BROWSER)
attempts	String	The number of failed login attempts (TOO_MANY_FAILED_ATTEMPTS)
distance_km	String	Distance in km (TRAVEL_SPEED)
distance_mi	String	Distance in mi (TRAVEL_SPEED)
speed_kmh	String	Speed in km/h (TRAVEL_SPEED)
speed_mph	String	Speed in mi/h (TRAVEL_SPEED)
existing_countries	String	A comma-separated list of countries for existing <i>User Sessions</i> for the user (COUNTRY_MISMATCH)

# Backup and recovery of the Awingu Environment

## Introduction

The Awingu platform allows to generate an off-site backup of the Awingu environment.

To backup an external database, please refer to the snapshot capabilities of MS SQL or PostgreSQL.

## Backup

Awingu saves the backup to local disk every day. You can retrieve this file and save it on another system via SFTP so that in case of a database or disk failure, you can recover your Awingu environment.

This backup includes:

- Basic configuration info of the appliance itself (mostly the options displayed during the installation).
- Vault and vault unlock tokens (if applicable/optional).
- Internal database (if applicable).
- Some encryption keys.

Some data is not stored into the database and won't be recovered:

- Metering data (in the Dashboard)
- Shares

The backup settings are found under **System Settings > Global > Connectivity > Environment Backups**

To download the backup from the Awingu environment:

- You need an SFTP capable client (graphical tool: FileZilla or Bitvise SSH Client; Linux command-line: sftp)
- Connect to the IP or FQDN of the datastore node, on port 22. For a single node VM, the datastore is located on the Awingu VM.
- Enter the username/password defined in System Settings

## Restore

To recover from a **broken internal database**, you can upload a previously downloaded backup to the Awingu appliance via SFTP or use a backup which is still available on the Awingu appliance.

To recover from **broken Awingu node(s)**, you can deploy a new appliance and import the environment backup during the installation wizard. (Additional Awingu nodes will not be added automatically after the initial restore, they need to be added again manually).

You can list the available backups on an appliance by executing the **environment-backup-list** action from the [Troubleshoot](#) page.

Same configuration and credentials apply for downloading or uploading dumps using SFTP.

After uploading a backup to restore to, execute the **environment-backup-restore** action from the [Troubleshoot](#) page.

If you restored to fresh new appliance, you will need to re-enter the Certificate and Private key (per domain: Configure > User Connector > Federated Authentication) when Single Sign-On is configured



- When restoring an Awingu environment to the same appliance(s) (using the troubleshoot action), each appliance needs to have the same host name and Awingu version.
- When restoring an Awingu environment to a new appliance (upload environment backup during installation), the Awingu appliance and environment backup need to be of the same Awingu version.
- It is recommended to reboot the appliance(s) after the restore is completed.